The tocloft package*

Author: Peter Wilson, Herries Press
Maintainer: LaTeX Project, Will Robertson

2026/10/30

Abstract

The tocloft package provides means of controlling the typographic design of the Table of Contents, List of Figures and List of Tables. New kinds of 'List of …' can be defined.

The package has been tested with the tocbibind, minitoc, ccaption, subfigure, float, fncychap, and hyperref packages.

Contents

1 Introduction **2**
1.1 Compatibility with \DocumentMetadata and the tagging support 2
1.2 Legacy LaTeX's methods 3

2 The tocloft package **7**
2.1 Package options 7
2.2 Changing the titles 7
2.3 Typesetting the entries 8
2.4 New list of… 13
2.5 Experimental utilities 16
2.6 Usage with other packages 17

3 The package code **18**
3.1 Support for the subfigure package 43
3.2 New list of… 46
3.3 Switching page numbering 51
3.4 Experimental utilities 53

Index **57**

List of Figures

1 Layout of a ToC (LoF, LoT) entry 4

*This file (tocloft.dtx) has version number v3.0d, last revised 2026/10/30. Issues can be reported at https://github.com/LaTeX-Package-Repositories/herries-press

List of Tables

1 Indents and Numwidths 5

1 Introduction

In the standard classes the typographic design of the Table of Contents (ToC), the List of Figures (LoF) and List of Tables (LoT) is fixed or, more precisely, it is buried within the class definitions. The tocloft package provides handles for an author to change the design to meet the needs of the particular document.

Elements of the package were developed as part of a class and package bundle for typesetting ISO standards [Wil96b]. This manual is typeset according to the conventions of the LaTeX DOCSTRIP utility which enables the automatic extraction of the LaTeX macro source files [GMS94].

Section 2 describes the usage of the package. Commented source code for the package is in Section 3.

The package has been tested in combination with at least the tocbibind package [Wil00], the minitoc package [Dru99], the ccaption package [Wil01], the subfigure package [Coc95] (versions 2.0 and 2.1), the algorithm package [Wil96a] (which, in turn, calls the float package [Lin95]) and the fncychap package [Lin97]. It also works with the hyperref package. Please send me any comments as to how you think that the package can be improved, or of any interesting examples of how you have used it.[1]

The package is not compatible with the KOMA-class. The memoir class suppresses the package and emulates it.

Version 3 adds support for `\DocumentMetadata` and tagging. It requires a current LaTeX format. The previous version can be loaded with

```
\usepackage{tocloft}[=v2]
```

1.1 Compatibility with `\DocumentMetadata` and the tagging support

To enable tagging of the various lists like the Table of Contents, the code loaded by `\DocumentMetadata` in LaTeX since 2025-11-01 changes various internals of the ToC processing and this clashes with the changes made by tocloft in various ways: In some cases `\DocumentMetadata` overwrites changes by tocloft and destroys its features, in other tocloft destroys tagging.

Version 3 of the package tries to make the tocloft package compatible with `\DocumentMetadata`. It is recommended to use this together with a current LaTeX.

Note that the code loaded by `\DocumentMetadata` is still changing. At some time ToC and similar lists will be reimplemented with templates and then more adaptions will be needed to keep tocloft compatible.

The following problems are handled by the new version if `\DocumentMetadata` is detected:

[1] Thanks to Rowland (`rebecca@astrid.u-net.com`), John Foster (`john@isjf.demon.co.uk`), Kasper (`kbg@dkik.dk`), Lee Nave (`nave@math.washington.edu`), and Andrew Thurber (`athurber@emba.uvm.edu`) for their suggestions.

`\@starttoc` tocloft patches the `\@starttoc` command to insert hooks like `\cfttocprehook` and `\cfttocposthook` but it does it only if `\@starttoc` has its original definition. As `\DocumentMetadata` changes `\@starttoc` the patch is lost. The new code reinstates the patch. Note that the hooks are before and after (outside) the tagging sockets that create the TOC-structure. They should not contain code that creates structures that are not allowed in this place.

Tagging of list entries In standard LaTeX the tagging support for the list entries is mostly handled through a redefinition of `\@dottedtocline`. As tocloft doesn't use `\@dottedtocline` (and also overwrites `\l@part` and `\l@chapter`) none of the entries were correctly tagged. Version 3.0 now add hooks and tagging sockets to all `\l@X` (`\l@part`, `\l@chapter` etc), to all `\cftXfillnum` commands and to the `\numberline` command to enable the tagging support.

Tagging of list headings If the package option `titles` is used, tocloft doesn't redefine the list commands and the list headings are tagged as in standard LaTeX. The various commands offered by the package to configure the look of the heading then do nothing.

If the package option `titles` is *not* used, tocloft doesn't use heading commands to typeset the headings of lists, instead it uses a combination of spacing and font commands to get the right look and the headings are not properly tagged as headings.

There are theoretically two options to add the proper tagging support: suitable structures could be added manually, e.g. with a tagging socket, or the headings could be typeset with standard heading commands always. The new code uses the second approach and passes the various tocloft commands as keys to the heading commands to emulate the configuration options.

This means that the headings can be configured by using the legacy tocloft commands, but also react (to some extent) if the template instances are edited. It also leads to small incompatible changes: As a heading command finishes with a `\par` the command `\cftafterZtitle` should not start with a newline command (and if used together with tagging, the tagging should be carefully checked.

1.2 Legacy LaTeX's methods

This is a general description of how LaTeX does the processing for a Table of Contents. As the processing for List of Figures and List of Tables is similar I will, without loss of generality, just discuss the ToC.

`\addcontentsline` LaTeX generates a `.toc` file if the document contains a `\tableofcontents` command. The sectioning commands[2] put entries into the `.toc` file by calling the LaTeX `\addcontentsline{`⟨*file*⟩`}{`⟨*kind*⟩`}{`⟨*title*⟩`}` command, where ⟨*file*⟩ is the file extension (e.g., `toc`), ⟨*kind*⟩ is the kind of entry (e.g., `section` or `subsection`), and ⟨*title*⟩ is the (numbered) title text. In the cases where there is a number, the ⟨*title*⟩ argument is given in the form `{\numberline{number} title-text}`.

NOTE: The hyperref package dislikes authors using `\addcontentsline`. To get it to work properly with hyperref you normally have to put `\phantomsection` (a macro defined within the hyperref package) immediately before `\addcontentsline`.

`\contentsline` The `\addcontentsline` command writes an entry to the given file in the form `\contentsline{`⟨*kind*⟩`}{`⟨*title*⟩`}{`⟨*page*⟩`}{`⟨*target*⟩`}` where ⟨*page*⟩ is the page number and

[2] For figures and tables it is the `\caption` command that populates the `.lof` and `.lot` files.




Figure 1: Layout of a ToC (LoF, LoT) entry

⟨*destination*⟩ is the anchor name (if hyperref is used). For each ⟨*kind*⟩, LaTeX provides a command `\l@kind{`⟨*title*⟩`}{`⟨*page*⟩`}` which performs the actual typesetting of the `\contentsline` entry.

`\@pnumwidth` `\@tocrmarg` `\@dotsep`

The general layout of a typeset entry is illustrated in Figure 1. There are three internal LaTeX commands that are used in the typesetting. The page number is typeset flushright in a box of width `\@pnumwidth`, and the box is at the righthand margin. If the page number is too long to fit into the box it will stick out into the righthand margin. The title text is indented from the righthand margin by an amount given by `\@tocrmarg`. Note that `\@tocrmarg` should be greater than `\@pnumwidth`. Some entries are typeset with a dotted leader between the end of the title title text and the righthand margin indentation. The distance, in *math units*[3] between the dots in the leader is given by the value of `\@dotsep`. In the standard classes the same values are used for the ToC, LoF and the LoT.

The standard values for these internal commands are:

- `\@pnumwidth` = 1.55em
- `\@tocrmarg` = 2.55em
- `\@dotsep` = 4.5

The values can be changed by using `\renewcommand`, in spite of the fact that the first two appear to be lengths.

Dotted leaders are not available for Part and Chapter ToC entries (nor for Section entries in the article class and its derivatives).

`\numberline`

Each `\l@kind` macro is responsible for setting the general *indent* from the lefthand margin, and the *numwidth*. The `\numberline{`⟨*number*⟩`}` macro is responsible for typesetting the number flushleft in a box of width *numwidth*. If the number is too long for the box then it will protrude into the title text. The title text is indented by (*indent* + *numwidth*) from the lefthand margin. That is, the title text is typeset in a block of width (`\linewidth` - *indent* - *numwidth* - `\@tocrmarg`).

Table 1 lists the standard values for the *indent* and *numwidth*. There is no explicit *numwidth* for a part; instead a gap of 1em is put between the number and the title text.

[3] There are 18mu to 1em.

Table 1: Indents and Numwidths (in ems)

Entry	Level	Chaptered		Otherwise	
		indent	numwidth	indent	numwidth
part	-1	0	—	0	—
chapter	0	0	1.5		
section	1	1.5	2.3	0	1.5
subsection	2	3.8	3.2	1.5	2.3
subsubsection	3	7.0	4.1	3.8	3.2
paragraph	4	10.0	5.0	7.0	4.1
subparagraph	5	12.0	6.0	10.0	5.0
figure/table	(1)	1.5	2.3	1.5	2.3

Note that for a sectioning command the values depend on whether or not the document class provides the `\chapter` command. Also, which somewhat surprises me, the table and figure entries are all indented.

`\@dottedtocline` Most of the `\l@kind` commands are defined in terms of the `\@dottedtocline` command. This command takes three arguments:
`\@dottedtocline{`⟨*seclevel*⟩`}{`⟨*indent*⟩`}{`⟨*numwidth*⟩`}`.
For example, one definition of the `\l@section` command is:
`\newcommand*{\l@section}{\@dottedtocline{1}{1.5em}{2.3em}}`
If it is necessary to change the default typesetting of the entries, then it is usually necessary to change these definitions (but the tocloft package gives you handles to easily alter things without having to know the LaTeX internals).

You can use the `\addcontentsline` command to add `\contentsline` commands to a file.

`\addtocontents` LaTeX also provides the `\addtocontents{`⟨*file*⟩`}{`⟨*text*⟩`}` command that will insert ⟨*text*⟩ into ⟨*file*⟩. You can use this for adding extra text and/or macros into the file, for processing when the file is typeset by `\tableofcontents` (or whatever other command is used for ⟨*file*⟩ processing, such as `\listoftables` for a `.lot` file).

As `\addcontentsline` and `\addtocontents` write their arguments to a file, any fragile commands used in their arguments must be `\protect`ed.

You can make certain adjustments to the ToC etc., layout without using any package. Some examples are:

- If your page numbers stick out into the righthand margin

  ```
  \renewcommand{\@pnumwidth}{3em} \renewcommand{\@tocrmarg}{4em}
  ```

  but using lengths appropriate to your document.

- To have the (sectional) titles in the ToC, etc., typeset ragged right with no hyphenation

  ```
  \renewcommand{\@tocrmarg}{2.55em plus1fil}
  ```

  where the value `2.55em` can be changed for whatever margin space you want.

- The dots in the leaders can be eliminated by increasing `\@dotsep` to a large value:

  ```
  \renewcommand{\@dotsep}{10000}
  ```

- To have dotted leaders in your ToC and LoF but not in your LoT:

  ```
  ...
  \tableofcontents
  \makeatletter \renewcommand{\@dotsep}{10000} \makeatother
  \listoftables
  \makeatletter \renewcommand{\@dotsep}{4.5} \makeatother
  \listoffigures
  ...
  ```

  For this document I used this method to double the dot spacing for the LoF with respect to that for the ToC. As you can see, it is much better that all dot leaders have the same spacing.

- To add a horizontal line across the whole width of the ToC below an entry for a Part:

  ```
  \part{Part title}
  \addtocontents{toc}{\protect\mbox{}\protect\hrulefill\par}
  ```

  Note that as both `\addtocontents` and `\addcontentsline` write their arguments to a file, it means that any *fragile* commands in their arguments must be protected by preceding each fragile command with `\protect`. The result of the example above would be the following two lines in the `.toc` file (assuming that it is the second Part and is on page 34):

  ```
  \contentsline {part}{II\hspace {1em}Part title}{34}{}%
  \mbox {}\hrulefill \par
  ```

  If the `\protect`s were not used, then the second line would instead be:

  ```
  \unhbox \voidb@x \hbox {}\unhbox \voidb@x \leaders \hrule \hfill \kern \z@ \par
  ```

- You may get undesired page breaks in the ToC. For example you may have a long multiline section title and in the ToC there is a page break between the lines. After your document is stable you can use `\addtocontents` at appropriate places in the body of the document to adjust the page breaking in the ToC. As examples:

  - `\addtocontents{toc}{\protect\newpage}` to force a page break.
  - `\addtocontents{toc}{\protect\enlargethispage{2\baselineskip}}` to make the page longer.
  - `\addtocontents{toc}{\protect\needspace{2\baselineskip}}` to specify that if there is not a vertical space of two baselines left on the page then start a new page (the `\needspace` macro is defined in the needspace package).

Remember, if you are modifying any command that includes an `@` sign then this must be done in either a `.sty` file or if in the document itself it must be surrounded by `\makeatletter` and `\makeatother`. For example, if you want to modify `\@dotsep` in the preamble to your document you have to do it like this:

```
\makeatletter
\renewcommand{\@dotsep}{9.0}
\makeatother
```

2 The tocloft package

The tocloft package provides means of specifying the typography of the Table of Contents (ToC), the List of Figures (LoF) and the List of Tables (LoT).

\tableofcontents
\listoffigures
\listoftables

The ToC, LoF, and LoT are printed at the point in the document where these commands are called, as per normal LaTeX. However, there is one difference between the standard LaTeX behaviour and the behaviour with the tocloft package. In the standard LaTeX classes that have `\chapter` headings, the ToC, LoF and LoT each appear on a new page. With the tocloft package they do not necessarily start new pages; if you want them to be on new pages you may have to specifically issue an appropriate command beforehand. For example:

```
 ...
\clearpage
\tableofcontents
\clearpage
\listoftables
...
```

\tocloftpagestyle

The `\thispagestyle` page style of the ToC, LoF and/or LoT is set by the command `\tocloftpagestyle{`⟨*style*⟩`}`, where ⟨*style*⟩ is one of the available page styles. The package initially sets `\tocloftpagestyle{plain}`.

2.1 Package options

The package takes the following options:

subfigure This option is required if, and only if, the tocloft and subfigure packages are being used together. The two packages can be specified in any order. Note that the subfigure is obsolete.

titles The titles option causes the titles of the ToC, LoF, and LoT lists to be typeset using the default LaTeX methods. This can be useful, for example, when the tocloft and fncychap packages are used together and the 'fancy' chapter styles should be used for the ToC, etc., titles.

If you use the titles option you can ignore the next section and continue reading at section 2.3.

2.2 Changing the titles

Commands are provided for controlling the appearance of the titles. Following LaTeX custom, the title texts are the values of the `\contentsname`, `\listfigurename` and `\listtablename` commands (stored inside `\cfttoctitlename`, `\cftloftitlename`, `\cftlottitlename`).

Similar sets of commands are provided for ToC, LoF and LoT title typesetting control. For convenience (certainly mine, and hopefully yours) in the following descriptions I will use `Z` to stand for 'toc' or 'lof' or 'lot'. For example, `\cftmarkZ` stands for `\cftmarktoc` or `\cftmarklof` or `\cftmarklot`.

\cftmarkZ

These macros set the appearance of the running heads on the ToC, LoF, and LoT pages. You probably don't need to change these.

\cftbeforeZtitleskip
\cftafterZtitleskip

These lengths control the vertical spacing before and after the titles. You can change

them from their default values by using `\setlength`.

`\cftZtitlefont` `\cftZtitlename` `\cftafterZtitle`

The code used for typesetting the ToC title looks like

```
{\cfttoctitlefont \cftZtitlename}{\cftaftertoctitle}\par
```

By default, `\cftZtitlefont` is defined as a font specification (e.g., `\Large\bfseries`), and `\cftafterZtitle` is empty. These commands can be changed (via `\renewcommand`) to change the typesetting. As examples:

- `\renewcommand{\cftZtitlefont}{\hfill\Large\itshape}` will result in a Large italic title typeset flushright.
- `\renewcommand{\cftZtitlefont}{\hfill\Large\bfseries}` together with `\renewcommand{\cftafterZtitle}{\hfill}` will give a centered Large bold title.
- Doing

  ```
  \renewcommand{\cftafterZtitle}{%
    \\[\baselineskip]\mbox{}\hfill{\normalfont Page}}
  ```

  will put the word 'Page' flushright on the line following the title. (If you do this, then you may need to decrease `\cftafterZtitleskip`). Note that if `\DocumentMetadata` is used, the command should not start with a `\\`, as it is will be inserted after the heading command.
- `\renewcommand{\cftafterZtitle}{\thispagestyle{empty}}` will make the page with the title empty (i.e., the page number will not be printed).

`\cfttitlecommand` `\cftchapter` `\cftsection`

`\cfttitlecommand` is used to typeset the heading of a list if `\DocumentMetadata` *is* used *and* the `titles` option is *not* used. It has one argument and by default it calls `\cftchapter` or `\cftsection` depending on if the class knows chapters or not.

2.3 Typesetting the entries

Commands are also provided to enable finer control over the typesetting of the different kinds of entries. The parameters defining the default layout of the entries are illustrated as part of the layouts package or in [GMS94, page 34], and are repeated in Figure 1.

`\Zdepth`

The command `\Zdepth{`⟨*number*⟩`}` is analogous to the standard `\tocdepth{`⟨*number*⟩`}` command, in that it specifies that entries in the new listing should not be typeset if their numbering level is greater than ⟨*number*⟩. The default definition is `\setcounter{Zdepth}{1}`. These commands are needed, for instance by users of packages such as `subcaption`, which will generate subfigure and subtable captions corresponding to a `lofdepth` and `lotdepth` of 2.

`\cftdot`

In the default ToC typesetting only the more minor entries have dotted leader lines between the sectioning title and the page number. The tocloft package provides for general leaders for all entries. The 'dot' in a leader is given by the value of `\cftdot`. Its default definition is `\newcommand{\cftdot}{.}` which gives the default dotted leader. By changing `\cftdot` you can use symbols other than a period in the leader. For example

```
\renewcommand{\cftdot}{\ensuremath{\ast}}
```

will result in a dotted leader using asterisks as the symbol.

\cftdotsep \cftnodots

Each kind of entry can control the separation between the dots in its leader (see below). For consistency though, all dotted leaders should use the same spacing. The macro \cftdotsep specifies the default spacing. Its value is a number. However, if the separation is too large then no dots will be actually typeset. The macro \cftnodots is a separation value that is 'too large'.

\cftsetpnumwidth \cftsetrmarg

The page numbers are typeset in a fixed width box. The command \cftsetpnumwidth{⟨*length*⟩} can be used to change the width of the box (LaTeX's internal \@pnumwidth). The title texts will end before reaching the righthand margin. \cftsetrmarg{⟨*length*⟩} can be used to set this distance (LaTeX's internal \@tocrmarg). Note that the length used in \cftsetrmarg should be greater than the length set in \cftsetpnumwidth. These values should remain constant in any given document.

\cftpnumalign

The page numbers are typeset in a box as described above. By default they are right-aligned which is suitable when the page numbers are aligned vertically on the page so their digits line up. For a design with fixed width between a ToC entry and its page number, say, a left alignment may be more suitable. This can be controlled by setting the \cftpnumalign macro to `l`, `c`, or `r` (just like \makebox):

```
\renewcommand{\cftpnumalign}{l}
```

\cftparskip

Normally the \parskip in the ToC, etc., is zero. This may be changed by changing the \cftparskip length. Note that the current value of \cftparskip is used for the ToC, LoF and LoT, but you can change the value before calling \tableofcontents or \listoffigures or \listoftables if one or other of these should have different values (which is not a good idea).

In the following I will use `X` to stand for the following:

- `part` for \part titles
- `chap` for \chapter titles
- `sec` for \section titles
- `subsec` for \subsection titles
- `subsubsec` for \subsubsection titles
- `para` for \paragraph titles
- `subpara` for \subparagraph titles
- `fig` for figure \caption titles
- `subfig` for subfigure \caption titles
- `tab` for table \caption titles
- `subtab` for subtable \caption titles

\cftbeforeXskip

This controls the vertical space before an entry. It can be changed by using \setlength.

\cftXindent

This controls the indentation of an entry from the left margin (*indent* in Figure 1). It can be changed using \setlength.

\cftXnumwidth

This controls the space allowed for typesetting title numbers (*numwidth* in Figure 1).

It can be changed using \setlength. Second and subsequent lines of a multiline title will be indented by this amount.

The remaining commands are related to the specifics of typesetting an entry. This is a simplified pseudo-code version for the typesetting of numbered and unnumbered entries.

```
{\cftXfont {\cftXpresnum SNUM\cftXaftersnum\hfil} \cftXaftersnumb TITLE}%
        {\cftXleader}{\cftXpagefont PAGE}\cftXafterpnum\cftXpnumfinal\par

{\cftXfont TITLE}{\cftXleader}{\cftXpagefont PAGE}\cftXafterpnum\cftXpnumfinal\par
```

where SNUM is the section number, TITLE is the title text and PAGE is the page number. In the numbered entry the pseudo-code
{\cftXpresnum SNUM\cftaftersnum\hfil}
is typeset within a box of width \cftXnumwidth.

\cftXfont This controls the appearance of the title (and its preceding number, if any). It may be changed using \renewcommand.

\cftXpresnum \cftXaftersnum \cftXaftersnumb \cftpartinitnumwidth Normally the section number is typeset within a box of width \cftXnumwidth. Within the box the macro \cftXpresnum is first called, then the number is typeset, and next the \cftXaftersnum macro is called after the number is typeset. The last command within the box is \hfil to make the box contents flushleft. After the box is typeset the \cftXaftersnumb macro is called before typesetting the title text. All three of these can be changed by \renewcommand. By default they are defined to do nothing.

In the standard classes the ToC entry for a \part is just typeset as the number and title, followed by the page number, with the \cftpartpresnum macro being called before typesetting the number and title. Due to LaTeX idiosyncrasies, \cftpartpresnum may become doubled in the output if a third-party package behaves differently to that of the default internal LaTeX commands. The tocloft package contains specific code to prevent this in the case of the KomaScript classes and for the titlesec package; please contact the maintainer to add further corrections if you discover other packages which also exhibit this mis-behaviour.

When a standard class is used the entry for \part doesn't use \numberline and so \cftpartaftersnum and \cftpartaftersnumb macros have no effect (but they may do something if a non-standard class is used). This changes if \DocumentMetadata is used: then also \part uses \numberline. To allow to adapt the formatting to the one used in the standard classes, the command uses \cftpartinitnumwidth to reset the width of the box with the number to the natural width. Its default definition is

```
\newcommand{\cftpartinitnumwidth}[1]{\settowidth\@tempdima{#1}}
```

\cftXleader \cftXdotsep \cftXleader defines the leader between the title and the page number; it can be changed by \renewcommand. The spacing between any dots in the leader is controlled by \cftXdotsep (\@dotsep in Figure 1). It can be changed by \renewcommand and its value must be either a number (e.g., 6.6 or \cftdotsep) or \cftnodots (to disable the dots). The spacing is in terms of *math units* where there are 18mu to 1em.

\cftXfillnum This commands typesets the leader. It contains the sockets for tagging support and should normally not be redefined by a user.

\cftXpagefont This defines the font to be used for typesetting the page number. It can be changed by \renewcommand.

\cftXafterpnum This macro is called after the page number has been typeset. Its default is to do nothing. It can be changed by \renewcommand.

\cftXpnumfinal This macro is called after \cftXafterpnum. By default it contains a pair of kerns

(stored in the command \cftpnumfinaldefault) that with microtype suppresses protrusion in this place. Such kerns are also used in the LaTeX kernel and normally there should be no need to remove or change them, but with this command it is possible. It can be changed by \renewcommand.

\cftpnumfinaldefault The default kerns used in \cftXpnumfinal.

\cftsetindents The command \cftsetindents{⟨*entry*⟩}{⟨*indent*⟩}{⟨*numwidth*⟩} sets the ⟨*entry*⟩'s *indent* to the length ⟨*indent*⟩ and its *numwidth* to the length ⟨*numwidth*⟩. The ⟨*entry*⟩ argument is the name of one of the standard entries (e.g., subsection) or the name of entry that has been defined with the tocloft package. For example
\cftsetindents{figure}{0em}{1.5em}
will make figure entries left justified.

Various effects can be achieved by changing the definitions of \cftXfont, \cftXaftersnum, \cftXaftersnumb, \cftXleader and \cftXafterpnum, either singly or in combination. For the sake of some examples, assume that we have the following initial definitions

```
\newcommand{\cftXfont}{}
\newcommand{\cftXaftersnum}{}
\newcommand{\cftXaftersnumb}{}
\newcommand{\cftXleader}{\cftdotfill{\cftXdotsep}}
\newcommand{\cftXdotsep}{\cftdotsep}
\newcommand{\cftXpagefont}{}
\newcommand{\cftXafterpnum}{}
```

(Note that the same font should be used for the title, leader and page number to provide a coherent appearance).

- To eliminate the dots in the leader:

  ```
  \renewcommand{\cftXdotsep}{\cftnodots}
  ```

- To put something (e.g., a name) before the title (number):

  ```
  \renewcommand{\cftXpresnum}{SOMETHING }
  ```

- To add a colon after the section number:

  ```
  \renewcommand{\cftXaftersnum}{:}
  ```

- To put something before the title number, add a colon after the the title number, set everything in bold font, and start the title text on the following line:

  ```
  \renewcommand{\cftXfont}{\bfseries}
  \renewcommand{\cftXleader}{\bfseries\cftdotfill{\cftXdotsep}}
  \renewcommand{\cftXpagefont}{\bfseries}
  \renewcommand{\cftXpresnum}{SOMETHING }
  \renewcommand{\cftXaftersnum}{:}
  \renewcommand{\cftXaftersnumb}{\\}
  ```

  If you are adding text in the number box in addition to the number, then you will probably have to increase the width of the box so that multiline titles have a neat vertical alignment; changing box widths usually implies that the indents will require modification as well.[4] One possible method of adjusting the box width for the above example is:

[4] Lyndon Dudding (lyndon.dudding@totalise.co.uk) discovered this.

```
\newlength{\mylen}   % a "scratch" length
\settowidth{\mylen}{\bfseries\cftXpresnum\cftXaftersnum} % extra space
\addtolength{\cftXnumwidth}{\mylen} % add the extra space
```

- To set the section numbers flushright:[5]

```
\setlength{\mylen}{0.5em}   % need some extra space at end of number
\renewcommand{\cftXpresnum}{\hfill}  % note the double `l'
\renewcommand{\cftXaftersnum}{\hspace*{\mylen}}
\addtolength{\cftXnumwidth}{\mylen}
```

  In the above, the added initial `\hfill` in the box overrides the final `\hfil` in the box, thus shifting everything to the right hand end of the box. The extra space is so that the number is not typeset immediately at the left of the title text.

- To set the entry ragged left (but this only looks good for single line titles):

```
\renewcommand{\cftXfont}{\hfill\bfseries}
\renewcommand{\cftXleader}{}
```

- To set the page number immediately after the entry text instead of at the righthand margin:

```
\renewcommand{\cftXleader}{}
\renewcommand{\cftXafterpnum}{\cftparfillskip}
\renewcommand{\cftpnumalign}{l}
```

`\cftparfillskip` By default the `\parfillskip` value is locally set to fill up the last line of a paragraph. Just changing `\cftXleader` puts horrible interword spaces into the last line of the title. The `\cftparfillskip` command is part of the tocloft package and is provided just so that the above effect can be achieved. In addition, this is a good example of when it would be suitable to change the alignment of the page number box.

- To remove the space inserted between table and figure caption entries between chapters:

```
\begingroup
  \renewcommand*{\addvspace}[1]{}
  \listoftables
  \listoffigures
\endgroup
```

`\cftpagenumbersoff` `\cftpagenumberson` The command `\cftpagenumbersoff{`⟨*entry*⟩`}` will eliminate the page numbers for ⟨*entry*⟩ in the listing, where ⟨*entry*⟩ is the name of one of the standard kinds of entries (e.g., `subsection`, or `figure` — including `subfigure` if the subfigure package is used — etc.), or the name of a new entry defined with the tocloft package.

The command `\cftpagenumberson{`⟨*entry*⟩`}` reverses the effect of a corresponding `\cftpagenumbersoff`.

One question that appeared on the `comp.text.tex` newsgroup asked how to get the titles of Appendices list in the ToC *without* page numbers. Here is a simple way of doing it, assuming the document has chapters

[5] With thanks to David Holz (`lbda@earthlink.net`) for requesting this.

```
...
\appendix
\addtocontents{toc}{\cftpagenumbersoff{chapter}}
\chapter{First appendix}
```

If there are other chaptered headings to go into the ToC after the appendices, then it will be necessary to do a similar
`\addtocontents{toc}{\cftpagenumberson{chapter}}`
to restore the page numbering in the ToC.

Similarly, if you are using the subfigure package you may want to eliminate the page numbers for the subfigure captions. This can be accomplished by:
`\cftpagenumbersoff{subfigure}`

At this point, I leave it up to your ingenuity as to other effects that you can achieve. However, if you come up with further examples, let me know for possible inclusion in a later version of this document.

2.4 New list of...

`\newlistof` The command `\newlistof[`⟨*within*⟩`]{`⟨*entry*⟩`}{`⟨*ext*⟩`}{`⟨*listofname*⟩`}` creates a new List of …, and assorted commands to go along with it.

The first required argument, ⟨*entry*⟩ is used to define a new counter called `entry`. The optional ⟨*within*⟩ argument can be used so that `entry` gets reset to one every time the counter called `within` is changed. That is, the first two arguments are equivalent to calling `\newcounter{`⟨*entry*⟩`}[`⟨*within*⟩`]`.

The next argument, ⟨*ext*⟩, is the file extension for the new List of. The last argument, ⟨*listofname*⟩, is the text for the heading of the new List of. As an example:

```
\newcommand{\listanswername}{List of Answers}
\newlistof[chapter]{answer}{ans}{\listanswername}
```

will create a new `answer` counter that will be reset at the start of each `\chapter{...}`. Any answer titles will be written to the file `jobname.ans` and `\listanswername` will be used as the list heading. A command `\listofanswer` is created which can be used just like the `\listoftables` or `\tableofcontents` commands to generate a listing. It is up to you to specify how the entries are put into the new List of Answers. Here is a very simple example, remembering that an `answer` counter has been created.

```
\newcommand{\answer}[1]{%
  \refstepcounter{answer}
  \par\noindent\textbf{Answer \theanswer. #1}
  \addcontentsline{ans}{answer}{\protect\numberline{\theanswer}#1}\par}
```

which, when used like:
`\answer{Hard} The \ldots` will print as:
Answer 1. Hard
The …

As mentioned above, the `\newlistof` command creates several new commands, most of which you should now be familiar with. For convenience, assume that `\newlistof{X}{ZZ}{...}` has been issued; so `X` is the name of the new counter and corresponds to the `X` in section 2.3, and `ZZ` is the new file extension and corresponds to the `Z` in section 2.2. Then, among others, the following new commands will be made available.

The five commands, `\cftmarkZZ`, `\cftbeforeZZtitleskip`, `\cftafterZZtitleskip`, `\cftZZtitlefont`, and `\cftafterZZtitle`, are analogous to the commands of the same names described in section 2.2.

`\listofX` The command `\listofX` is similar to `\listoftables`, etc., in that it typesets the new listing at the point where it is called.

`\ZZdepth` The command `\ZZdepth{`⟨*number*⟩`}` is analogous to the standard `\tocdepth{`⟨*number*⟩`}` command, in that it specifies that entries in the new listing should not be typeset if their numbering level is greater than ⟨*number*⟩. The default definition is `\setcounter{ZZdepth}{1}`.

`\newlistentry` The command `\newlistentry[`⟨*within*⟩`]{`⟨*entry*⟩`}{`⟨*ext*⟩`}{`⟨*level-1*⟩`}` creates new commands for typesetting a new kind of entry in a listing. It is used internally by the `\newlistof` command but may be used independently.

The first required argument, ⟨*entry*⟩ is used to define a new counter called `entry`. The optional ⟨*within*⟩ argument can be used so that `entry` gets reset to one every time the counter called `within` is changed. That is, the first two arguments are equivalent to calling `\newcounter{`⟨*entry*⟩`}[`⟨*within*⟩`]`. The second required argument, ⟨*ext*⟩, is the file extension for the entry listing. The last argument, ⟨*level-1*⟩, is a number specifying the numbering level minus one, of the entry in a listing. For example, the command
`\newlistof[chapter]{answer}{ans}{\listanswername}`
will call the command:
`\newlistentry[chapter]{answer}{ans}{0}`

Calling `\newlistentry` creates several new commands. Assuming that it is called as `\newlistentry[within]{X}{ZZ}{N}`, where `X` and `ZZ` are similar to the previous uses of them, and `N` is an integer number, then the following commands are made available.

The set of commands `\cftbeforeXskip`, `\cftXfont`, `\cftXpresnum`, `\cftXaftersnum`, `\cftXaftersnumb`, `\cftXleader`, `\cftXdotsep`, `\cftXpagefont`, `\cftXafterpnum`, and `\cftXpnumfinal` are analogous to the commands of the same names described in section 2.3. Their default values are also as described earlier.

The default values of `\cftXindent` and `\cftXnumwidth` are set according to the value of the ⟨*level-1*⟩ argument (i.e., `N` in this example). For `N=0` the settings correspond to those for sections in non-chaptered documents, as listed in Table 1. For `N=4` the settings correspond to subparagraphs in non-chaptered documents, and for intermediate values correspond to the matching sectional division in chaptered documents. For values of `N` less than zero or greater than four, or for non-default values, use the `\cftsetindents` command to set the values.

`\l@X` `\l@X` is an internal command that typesets an entry in the list, and is defined in terms of the above `\cft*X*` commands. It will not typeset an entry if `\ZZdepth` is `N` or less, where `ZZ` is the listing's file extension.

`\theX` The command `\theX` prints the value of the `X` counter. It is initially defined so that it prints arabic numerals. If the optional ⟨*within*⟩ argument is used, `\theX` is defined as `\renewcommand{\theX}{\thewithin.\arabic{X}}` otherwise as `\renewcommand{\theX}{\arabic{X}}`.

As an example of the independent use of `\newlistentry`, the following will set up for sub-answers.

```
\newlistentry[answer]{subanswer}{ans}{1}
\cftsetindents{subanswer}{1.5em}{3.0em}
\renewcommand{\thesubanswer}{\theanswer.\alph{subanswer}}
\newcommand{\subanswer}[1]{%
```

```
   \refstepcounter{subanswer}%
   \par\textbf{\thesubanswer) #1}%
   \addcontentsline{ans}{subanswer}{\protect\numberline{\thesubanswer}#1}}
\setcounter{ansdepth}{2}
```

And then:

```
\answer{Harder} The \ldots
  \subanswer{Reformulate the problem} It assists \ldots
```

will be typeset as:

Answer 2. Harder

The …

2.a) Reformulate the problem It assists …

By default the answer entries will appear in the List of Answers listing (typeset by the `\listofanswer` command). In order to get the subanswers to appear, the `\setcounter{ansdepth}{2}` command was used above.

To turn off page numbering for the subanswers, do
`\cftpagenumbersoff{subanswer}`

As another example of `\newlistentry`, suppose that an extra sectioning division below `subparagraph` is required, called `subsubpara`. The `\subsubpara` command itself can be defined via the LaTeX kernel `\@startsection` command. Also it is necessary to define a `\subsubparamark` macro, a new `subsubpara` counter, a `\thesubsubpara` macro and a `\l@subsubpara` macro. Using the tocloft package's `\newlistentry` takes care of most of these as shown below (remember the caveats about commands with `@` signs in them).

```
\newcommand{\subsubpara}{\@startsection{subpara}%
   {6}%                                              level
   {\parindent}%                        indent from left margin
   {3.25ex \@plus1ex \@minus .2ex}%       skip above heading
   {-1em}%       runin heading with 1em between title & text
   {\normalfont\normalsize\itshape}% italic number and title
}
\newlistentry[subparagraph]{subsubpara}{toc}{5}
\cftsetindents{subsubpara}{14.0em}{7.0em}
\newcommand*{\subsubparamark}[1]{}     % gobble heading mark
```

Each List of…uses a file to store the list entries, and these files must remain open for writing throughout the document processing. TeX has only a limited number of files that it can keep open, and this puts a limit on the number of listings that can be used. For a document that includes a ToC but no other extra ancillary files (e.g., no index or bibliography output files) the maximum number of LoX's, including a LoF and LoT, is no more than about eleven. If you try and create too many new listings LaTeX will respond with the error message:

```
No room for a new write
```

If you get such a message the only recourse is to redesign your document.

The tocloft package does not provide a simple means of specifying new Lists of Floats or float environments. For those, I recommend the ccaption package [Wil01].

2.5 Experimental utilities

The macros described in this section are even more experimental than those described previously.

\cftchapterprecis Some old style novels, and even some modern text books,[6] include a short synopsis of the contents of the chapter either immediately after the chapter heading or in the Toc, or in both places.

The command `\cftchapterprecis{`⟨*text*⟩`}` prints its argument both at the point in the document where it is called, and also adds it to the `.toc` file. For example:

```
...
\chapter{} % first chapter
\cftchapterprecis{Our hero is introduced; family tree; early days.}
...
```

If tagging is enabled, the toc entry is currently tagged as an individual toc entry.

\cftchapterprecishere \cftchapterprecistoc The `\cftchapterprecis` command calls these two commands to print the text in the document (the `\...here{`⟨*text*⟩`}` command) and to put it into the ToC (the `\...toc{`⟨*text*⟩`}` command). These can be used individually if required.

Sometimes it may be desirable to make a change to the global parameters for an individual entry. For example, a figure might be placed on the end paper of a book (the inside of the front or back cover), and this needs to be placed in a LoF with the page number set as, say 'inside front cover'. If 'inside front cover' is typeset as an ordinary page number it will stick out into the margin. Therefore, the parameters for this particular entry need to be changed.

\cftlocalchange The command `\cftlocalchange{`⟨*file*⟩`}{`⟨*pnumwidth*⟩`}{`⟨*tocrmarg*⟩`}` will write an entry into ⟨*file*⟩ to reset the global parameters. The command should be called again after any special entry to reset the parameters back to their usual values. Any fragile commands used in the arguments must be protected.

\cftaddtitleline The command `\cftaddtitleline{`⟨*file*⟩`}{`⟨*kind*⟩`}{`⟨*title*⟩`}{`⟨*page*⟩`}` will write a `\contentsline` entry into ⟨*file*⟩ for a ⟨*kind*⟩ entry with title ⟨*title*⟩ and page number ⟨*page*⟩. That is, an entry is made of the form:

`\contentsline{kind}{title}{page}{target}`

Any fragile commands used in the arguments must be protected.

\cftaddnumtitleline The command `\cftaddnumtitleline{`⟨*file*⟩`}{`⟨*kind*⟩`}{`⟨*num*⟩`}{`⟨*title*⟩`}{`⟨*page*⟩`}` is similar except that it also includes ⟨*num*⟩ as the argument to the `\numberline`. That is, an entry is made of the form:

`\contentsline{kind}{\numberline{num} title}{page}{target}`

Any fragile commands used in the arguments must be protected.

As an example of the use of these commands, noting that the default LaTeX values for `\@pnumwidth` and `\@tocrmarg` are 1.55em and 2.55em respectively, one might do the following for a figure on the frontispiece page.

```
...
% this is the frontispiece page with no number
% draw or import the picture (with no \caption)
\cftlocalchange{lof}{4em}{5em} % make pnumwidth big enough for
                               % frontispiece and change margin to suit
\cftaddtitleline{lof}{figure}{The title}{frontispiece}
```

[6] For example, Robert Sedgewick, *Algorithms*, Addison-Wesley, 1983.

```
\cftlocalchange{lof}{1.55em}{2.55em} % return to normal settings
...
```

Recall that a `\caption` command will put an entry in the `.lof` file, which is not wanted here. If a caption is required, then you can either craft one yourself or, assuming that your general captions are not too exotic, use the `\legend` command from the ccaption package. If the illustration is numbered, use the `\cftaddnumtitleline` command instead of `\cftaddtitleline`.

`\cftZprehook` `\cftZposthook`

It's surprisingly difficult to achieve multicolumn ToCs; can you guess what the problem is to write the following?

```
\begin{multicols}{2}
\tableofcontents
\end{multicols}
```

Probably the easiest way to do it in regular LaTeX is something like

```
\RequirePackage{multicol}
\AtBeginDocument{\addtocontents{toc}{\protect\begin{multicols}{2}}}
\AtEndDocument  {\addtocontents{toc}{\protect\end  {multicols}}}
```

This method of writing to the `.toc` file is most flexible for trying to control the typesetting output within the table of contents.

To make this *slightly* easier with tocloft, the following macros are available: `\cftZprehook` and `\cftZprehook`, where `Z` is `toc`, `lof`, `lot`, etc. If these are defined, they insert material just before the actual typesetting of the entries of the table of contents and so on. A multicolumn ToC can therefore be achieved with this:

```
\RequirePackage{multicol}
\renewcommand\cfttocprehook{\begin{multicols}{2}}
\renewcommand\cfttocposthook{\end{multicols}}
```

2.6 Usage with other packages

The tocloft and tocbibind packages can be used together in the same document. The tocbibind package provides easy means of adding document elements like the bibliography or the index to the Table of Contents. However there is one known potential problem:

- If the argument to the `\tocotherhead` command is other than one of the normal sectioning divisions (i.e., part through to sub-paragraph) such as `\tocotherhead{clause}`, then this will almost certainly cause a problem (as the tocloft package will not know how to define the corresponding `\l@clause` command). In such a case you will have to supply the appropriate macros yourself.

`\@cftbsnum` `\@cftasnum` `\@cftasnumb`

Some packages, like the float package by Anselm Lingnau, enable the creation of other kinds of *List of ...*. The tocloft package is only minimally able to change the formatting of these, principally because the packages are independent of each other and, in the case of the float package, new kinds of float environments and their associated lists can be created on the fly at any point in a document. Some aspects of the typesetting are controlled by `\@cftbsnum`, `\@cftasnum` and `\@cftasnumb` commands. These are equivalent to the `\cftXpresnum`, `\cftXaftersnum` and `\cftXaftersnumb` commands described earlier. By default they are defined to do nothing, but may be renewed to do something.

The tocloft and minitoc packages have an unfortunate interaction,[7] which fortunately can be fixed. In the normal course of events, when minitoc is used in a chaptered document it will typeset section entries in the minitocs in bold font. If tocloft is used in conjunction with minitoc, then the minitoc section entries are typeset in the normal font, except for the page numbers which are in bold font, while the ToC section entries are all in normal font.

One cure, if you want the minitoc section entries to be all in normal font is to put:

```
\renewcommand{\mtcSfont}{\small\normalfont}
```

in the preamble.

Otherwise, the cure is the following incantation:

```
\renewcommand{\cftsecfont}{\bfseries}
\renewcommand{\cftsecleader}{\bfseries\cftdotfill{\cftdotsep}}
\renewcommand{\cftsecpagefont}{\bfseries}
```

To have the section entries in both the ToC and the minitocs in bold then put the incantation in the preamble. To have only the minitoc section entries in bold while the ToC entries are in the normal font, put the incantation between the `\tableofcontents` command and the first `\chapter` command.

In general, use with other packages that redefine any of the macros that tocloft also modifies is likely to be problematic.

3 The package code

```
⟨*usc⟩
\RequirePackage{etoolbox}
```

In order to try and avoid name clashes with other packages, each internal name will include the character string `@cft`.

`\@cftifundefined` Due to a conflict with how this package and fancyhdr checked for undefinedness.

```
\newcommand\@cftifundefined[1]{%
  \begingroup\expandafter\expandafter\expandafter\endgroup
  \expandafter\ifx\csname #1\endcsname\relax
    \expandafter\@firstoftwo
  \else
    \expandafter\@secondoftwo
  \fi}
```

(*End of definition for* `\@cftifundefined`.)

`\@cftquit` We will be using either chapter or section type headings for the ToC, etc., so we need to `\if@cfthaschapter` know which of these the document class supports.

```
\newcommand{\@cftquit}{}
\newif\if@cfthaschapter
```

(*End of definition for* `\@cftquit` *and* `\if@cfthaschapter`.)

[7] Discovered by Lyndon Dudding (`lyndon.dudding@totalise.co.uk`).

`\if@cftkoma` The koma classes have different defaults than the standard classes, so we need to know if a koma class has been loaded.

```
\newif\if@cftkoma
\@cftkomafalse
\@ifclassloaded{scrartcl}{\@cftkomatrue}{}
\@ifclassloaded{scrreprt}{\@cftkomatrue}{}
\@ifclassloaded{scrbook}{\@cftkomatrue}{}
```

(*End of definition for* `\if@cftkoma`.)

`\if@cfttitlesec`

```
\newif\if@cfttitlesec
\AtBeginDocument{\@ifpackageloaded{titlesec}{\@cfttitlesectrue}{}}
```

(*End of definition for* `\if@cfttitlesec`.)

Issue a warning if there are no recognised sectional divisions and then skip the rest of the package code.

```
\@cftifundefined{chapter}{%
  \@cfthaschapterfalse
  \@cftifundefined{section}{%
    \PackageWarning{tocloft}%
      {I don't recognize any sectional divisions so I'll do nothing}
    \renewcommand{\@cftquit}{\endinput}
    }{\PackageInfo{tocloft}{The document has section divisions}}
  }{\@cfthaschaptertrue
    \PackageInfo{tocloft}{The document has chapter divisions}}
```

Perhaps quit now.

```
\@cftquit
```

Use chapter style if `\if@cfthaschapter` is TRUE, otherwise section style.

`\if@cfttocbibind` A flag that is set TRUE iff the tocbibind package has been loaded. The 1998/11/15 version of tocbibind does not necessarily work well with tocloft.

```
\newif\if@cfttocbibind
\AtBeginDocument{%
  \@ifpackageloaded{tocbibind}{\@cfttocbibindtrue}{\@cfttocbibindfalse}
  \if@cfttocbibind
    \@ifpackagelater{tocbibind}{1998/11/16}{}{%
      \PackageWarning{tocloft}{%
You are using a version of the tocbibind package\MessageBreak
that is not compatible with tocloft.\MessageBreak
The results may be surprising.\MessageBreak
Consider installing the current version of tocbibind.}}
  \fi
}
```

(*End of definition for* `\if@cfttocbibind`.)

`\if@cftnctoc` A boolean used to implement the titles option. It is TRUE if the ToC, LoT, LoF titles should use the default styles.

```
\newif\if@cftnctoc\@cftnctocfalse
\DeclareOption{titles}{\@cftnctoctrue}
  %% \ProcessOptions\relax
```

(*End of definition for* `\if@cftnctoc`.)

`\if@cftsubfigopt` A boolean used to implement the subfigure option.

```
\newif\if@cftsubfigopt\@cftsubfigoptfalse
\DeclareOption{subfigure}{\@cftsubfigopttrue}
```

(*End of definition for* `\if@cftsubfigopt`.)

Process the options.

```
\ProcessOptions\relax

```

`\tocloftpagestyle` `\@cftpagestyle` A user-level macro to set the pagestyle for the first page of the ToC, etc. The default is the `plain` pagestyle.

```
\newcommand{\tocloftpagestyle}[1]{%
  \def\@cftpagestyle{\thispagestyle{#1}}}
\tocloftpagestyle{plain}

```

(*End of definition for* `\tocloftpagestyle` *and* `\@cftpagestyle`. *These functions are documented on page* 7.)

`\cftmarktoc` `\cftmarklof` `\cftmarklot` These three macros set the style for running heads. They are initialised to give the default appearance.

```
\newcommand{\cftmarktoc}{%
  \@mkboth{\MakeUppercase\cfttoctitlename}{\MakeUppercase\cfttoctitlename}}
\newcommand{\cftmarklof}{%
  \@mkboth{\MakeUppercase\cftloftitlename}{\MakeUppercase\cftloftitlename}}
\newcommand{\cftmarklot}{%
  \@mkboth{\MakeUppercase\cftlottitlename}{\MakeUppercase\cftlottitlename}}
\if@cftkoma
  \renewcommand{\cftmarktoc}{%
    \@mkboth{\cfttoctitlename}{\cfttoctitlename}}
  \renewcommand{\cftmarklof}{%
    \@mkboth{\cftloftitlename}{\cftloftitlename}}
  \renewcommand{\cftmarklot}{%
    \@mkboth{\cftlottitlename}{\cftlottitlename}}
\fi
```

(*End of definition for* `\cftmarktoc`, `\cftmarklof`, *and* `\cftmarklot`. *These functions are documented on page* 7.)

`\@cfttocstart` `\@cfttocfinish` Two macros to perform the actions at the beginning and end of the `\tableofcontents` command (and friends). `\@cfttocstart` deals with chaptered documents, ensuring that the ToC is typeset in a single column (see `classes.dtx` for the original code). These macros are also provided by the ccaption package.

```
\providecommand{\@cfttocstart}{%
  \if@cfthaschapter
    \if@twocolumn
      \@restonecoltrue\onecolumn
    \else
      \@restonecolfalse
    \fi
  \fi}
```

\@cfttocfinish resets, if required, twocolumn typesetting.

```
\providecommand{\@cfttocfinish}{%
  \if@cfthaschapter
    \if@restonecol\twocolumn\fi
  \fi}
```

(*End of definition for* `\@cfttocstart` *and* `\@cfttocfinish`.)

`\phantomsection` This is provided because the hyperref package screws with `\addcontentsline`.

```
\providecommand{\phantomsection}{}

```

(*End of definition for* `\phantomsection`.)

`\@cftdobibtoc` If the tocbibind package has been used and it has redefined `\tableofcontents` we need to cater for that. The contents of the definition are defined in tocbibind.

```
\newcommand{\@cftdobibtoc}{%
  \if@dotoctoc
    \if@bibchapter
      \phantomsection
      \addcontentsline{toc}{chapter}{\cfttoctitlename}
    \else
      \phantomsection
      \addcontentsline{toc}{\@tocextra}{\cfttoctitlename}
    \fi
  \fi}

```

(*End of definition for* `\@cftdobibtoc`.)

`\cftparskip` The `\parskip` local to the ToC, etc., is set to the length `\cftparskip`.

```
\newlength{\cftparskip}
\setlength{\cftparskip}{0pt}

```

(*End of definition for* `\cftparskip`. *This function is documented on page 9.*)

`\cftpnumfinaldefault` A kern pair used at the end of entries to avoid problems with protrusion.

```
\newcommand\cftpnumfinaldefault{\kern-\p@\kern\p@}
```

(*End of definition for* `\cftpnumfinaldefault`. *This function is documented on page 11.*)

`\cftZtitlename`

```
\newcommand\cfttoctitlename{\contentsname}
\newcommand\cftloftitlename{\listfigurename}
\newcommand\cftlottitlename{\listtablename}
```

(*End of definition for* `\cftZtitlename`. *This function is documented on page 8.*)

`\cfttitlecommand` This command is used to typeset the title if `\DocumentMetadata` *is* used *and* the `titles` option is *not* used.

```
\if@cfthaschapter
 \newcommand\cfttitlecommand[1]{\cftchapter{#1}}
\else
 \newcommand\cfttitlecommand[1]{\cftsection{#1}}
\fi
```

(*End of definition for* `\cfttitlecommand`. *This function is documented on page 8.*)

`\cftchapter`
`\cftsection`
`\cft@listname`

```
\newcommand\cft@listname{}
\IfDocumentMetadataTF
 {
   \@ifundefined{IfTemplateExistsTF}
    {
      \DeclareInstance{headformat}{cftchapter}{display}
       {
        , heading-indent    = 0pt
        , prefix-number-sep = \WordSpaceAmount{1}
        , title-format      = #1\UseName{cftafter\cft@listname title}
       }
     \DeclareDocumentCommand \cftchapter {O{}m}
     {%
       \renewcommand\cft@listname{#2}%
       \chapter
         [
           toc={},
           placement=normal,
           unnumbered,
           after-penalty-vspace=\dimeval{\UseName{cftbefore#2titleskip}-\topskip},
           after-vspace=\UseName{cftafter#2titleskip},
           final-code=\@cftpagestyle\@afterheading,
           heading-decls=\UseName{cft#2titlefont},
           headformat-instance=cftchapter,
           #1
         ] {\UseName{cft#2titlename}}%
     }
   \DeclareInstance{headformat}{cftsection}{hang}
    {
      , heading-indent = 0pt
      , title-format      = #1\UseName{cftafter\cft@listname title}
    }

   \DeclareDocumentCommand \cftsection {O{}m}
     {%
      \renewcommand\cft@listname{#2}%
      \section[
           toc={},
           placement=normal,
           unnumbered,
           before-vspace=\dimeval{\UseName{cftbefore#2titleskip}-\topskip},
           after-vspace=\UseName{cftafter#2titleskip},
           final-code=\@cftpagestyle\@afterheading,
           heading-decls=\tagpdfparaOff\UseName{cft#2titlefont}\tagpdfparaOn,
           headformat-instance=cftsection,
          #1
         ] {\UseName{cft#2titlename}}%
     }
    }
```

New code for the next release:

```
    {
```

```
      \DeclareInstance{headformat}{cftchapter}{display}
       {
        , heading-indent    = 0pt
        , separator-a       = \nobreakspace
       }
      \DeclareDocumentCommand \cftchapter {O{}m}
       {%
        \renewcommand\cft@listname{#2}%
        \chapter
          [
            toc={},
            placement=normal,
            unnumbered,
            after-penalty-vspace=\dimeval{\UseName{cftbefore#2titleskip}-\topskip},
            after-vspace=\UseName{cftafter#2titleskip},
            placement-end-code=\@cftpagestyle\@afterheading,
            heading-decls=\UseName{cft#2titlefont},
            headformat-instance=cftchapter,
            title-format      = ##1\UseName{cftafter\cft@listname title},
            #1
          ] {\UseName{cft#2titlename}}%
       }
      \DeclareInstance{headformat}{cftsection}{hang}
       {
         , heading-indent = 0pt
       }

      \DeclareDocumentCommand \cftsection {O{}m}
        {%
         \renewcommand\cft@listname{#2}%
         \section[
              toc={},
              placement=normal,
              unnumbered,
              before-vspace=\dimeval{\UseName{cftbefore#2titleskip}-\topskip},
              after-vspace=\UseName{cftafter#2titleskip},
              placement-end-code=\@cftpagestyle\@afterheading,
              heading-decls=\UseName{cft#2titlefont},
              headformat-instance=cftsection,
              title-format      = ##1\UseName{cftafter\cft@listname title},
             #1
            ] {\UseName{cft#2titlename}}%
        }
    }
  }
  {
   \DeclareDocumentCommand \cftchapter {O{}m}
    {%
      \addpenalty\@secpenalty
      \vspace*{\UseName{cftbefore#2titleskip}}%
      \@cftpagestyle
      {\interlinepenalty\@M
      {\UseName{cft#2titlefont}\UseName{cft#2titlename}}%
      {\UseName{cftafter#2title}}%
```

```
      \UseName{cftmark#2}%
      \par\nobreak
      \vskip \UseName{cftafter#2titleskip}%
      \@afterheading}%
    }
   \DeclareDocumentCommand \cftsection {O{}m}
    {%
      \addpenalty\@secpenalty
      \vspace{\UseName{cftbefore#2titleskip}}%
      \@cftpagestyle
      {\interlinepenalty\@M
      {\UseName{cft#2titlefont}\UseName{cft#2titlename}}%
      {\UseName{cftafter#2title}}%
      \UseName{cftmark#2}%
      \par\nobreak
      \vskip \UseName{cftafter#2titleskip}%
      \@afterheading}%
    }
  }
```

(*End of definition for* `\cftchapter`, `\cftsection`, *and* `\cft@listname`. *These functions are documented on page 8.*)

`\tableofcontents` This is a parameterised version of the default `\tableofcontents` command. Each class has its own definition, but we have to cater for all classes in one definition, hence some of the checks. The definition is modified after all packages have been loaded.
If the titles option has been used, then the command is not modified.

```
\AtBeginDocument{%
\if@cftnctoc
  % ensure \cftparskip is still set properly
  \let\OLD@starttoc\@starttoc
  \renewcommand{\@starttoc}[1]{%
    \begingroup
      \parskip=\cftparskip
      \OLD@starttoc{#1}%
    \endgroup
  }
\else
  \renewcommand{\tableofcontents}{%
    \@cfttocstart
```

Ensure that any previous paragraph has been finished. Within a group set the local paragraphing style and typeset the title.

```
    \par
    \begingroup
      \parindent\z@ \parskip\cftparskip
      \@cftmaketoctitle
```

If tocbibind has been used, then add the ToC name to the ToC.

```
      \if@cfttocbibind
        \@cftdobibtoc
      \fi
```

Finally, read the `.toc` file and finish up.

```
      \@starttoc{toc}%
    \endgroup
    \@cfttocfinish}
\fi
}
```

(*End of definition for* `\tableofcontents`. *This function is documented on page 7.*)

`\@cftmaketoctitle` This command typesets the title for the ToC.

```
\newcommand{\@cftmaketoctitle}{\cfttitlecommand{toc}}%
```

(*End of definition for* `\@cftmaketoctitle`.)

`\cftbeforetoctitleskip` `\cftaftertoctitleskip` These two lengths control the vertical spacing before and after the ToC title.

```
\newlength{\cftbeforetoctitleskip}
\newlength{\cftaftertoctitleskip}
```

Their values depend on whether the document has chapters or not. In chaptered documents the default ToC title is typeset as a `\chapter*`, otherwise as a `\section*`.

```
\if@cfthaschapter
  \setlength{\cftbeforetoctitleskip}{50pt}
  \setlength{\cftaftertoctitleskip}{40pt}
\else
  \setlength{\cftbeforetoctitleskip}{3.5ex \@plus 1ex \@minus .2ex}
  \setlength{\cftaftertoctitleskip}{2.3ex \@plus.2ex}
\fi
```

(*End of definition for* `\cftbeforetoctitleskip` *and* `\cftaftertoctitleskip`. *These functions are documented on page 7.*)

`\cfttoctitlefont` `\cftaftertoctitle` The ToC title is typeset in the style given by `\cfttoctitlefont`. The macro `\cftaftertoctitle` is called after typesetting the title. This is initialised to do nothing. Both these macros can be redefined to do other things (e.g., adding an `\hfill` to `\cfttoctitlefont` will make the title flushright).

```
\if@cfthaschapter
  \newcommand{\cfttoctitlefont}{\normalfont\Huge\bfseries}
  \if@cftkoma\renewcommand{\cfttoctitlefont}{\size@chapter\sectfont}\fi
\else
  \newcommand{\cfttoctitlefont}{\normalfont\Large\bfseries}
  \if@cftkoma\renewcommand{\cfttoctitlefont}{\size@section\sectfont}\fi
\fi
\newcommand{\cftaftertoctitle}{}
```

(*End of definition for* `\cfttoctitlefont` *and* `\cftaftertoctitle`. *These functions are documented on page 8.*)

`\cftsetpnumwidth` `\cftsetrmarg` Users commands for setting `\@pnumwidth` and `\@tocrmarg`.

```
\newcommand{\cftsetpnumwidth}[1]{\renewcommand{\@pnumwidth}{#1}}
\newcommand{\cftsetrmarg}[1]{\renewcommand{\@tocrmarg}{#1}}
```

(*End of definition for* `\cftsetpnumwidth` *and* `\cftsetrmarg`. *These functions are documented on page 9.*)

`\cftpnumalign` Alignment string (as input to `\makebox` for the page number box.

```
\newcommand{\cftpnumalign}{r}
```

(*End of definition for* `\cftpnumalign`. *This function is documented on page 9.*)

`\cftdot` `\cftdotfill` In the default ToC, a dotted line can be used to provide a leader between a title and the page number. The definition of this leader is buried in the `\@dottedtocline` command. The `\cftdotfill{`⟨*sep*⟩`}` command provides a parameterised version of the leader code, where ⟨*sep*⟩ is the separation between the dots in mu units. The symbol used for the 'dots' in the leader is given by the value of `\cftdot`. These macros are also provided by the ccaption package.

```
\providecommand{\cftdot}{.}
\providecommand{\cftdotfill}[1]{%
  \def\@tempa{#1}%
  \def\@tempb{\cftnodots}%
  \ifx\@tempa\@tempb
    \hfill
  \else
    \leaders\hbox{$\m@th\mkern #1 mu\hbox{\cftdot}\mkern #1 mu$}\hfill
  \fi
}
```

(*End of definition for* `\cftdot` *and* `\cftdotfill`. *These functions are documented on page 8.*)

`\cftdotsep` `\cftnodots` `\cftdotsep` holds the default dot separation, and is also provided by the ccaption package. If the kerns in `\cftdotfill` are large enough, then no dots will be printed. `\cftnodots` should be 'large enough'. (Actually, `\cftnodots` is now used as a flag for a conditional branch, so its numerical value isn't as important now.)

```
\providecommand{\cftdotsep}{4.5}
\newcommand{\cftnodots}{5000}
```

(*End of definition for* `\cftdotsep` *and* `\cftnodots`. *These functions are documented on page 9.*)

Now for the trickier bits regarding the typesetting of the ToC entries.

A `.toc` (also `.lof` and `.lot`) file consists of a list of
`\contentsline{`⟨*kind*⟩`}{`⟨*title*⟩`}{`⟨*page*⟩`}{`⟨*target*⟩`}`
commands, where ⟨*kind*⟩ is the kind of heading (e.g., `part` or `section` or `figure`), ⟨*title*⟩ is the title text (including the number), and ⟨*page*⟩ is the page number. ⟨*target*⟩ is set by hyperref or by the tagging code for links and structure references. The entries are inserted into the file by calling the `\addcontentsline{`⟨*file*⟩`}{`⟨*kind*⟩`}{`⟨*title*⟩`}` command, where ⟨*file*⟩ is the file extension (e.g., `toc`, `lot`) and the other arguments are the same as for the `\contentsline` command. (Arbitrary stuff may also be put into the file via the `\addtocontents{`⟨*file*⟩`}{`⟨*text*⟩`}` command). The typesetting of the `\contentsline` entries is performed by commands of the form `\l@kind`. The sectioning and captioning commands call `\addcontentsline` to insert their titles into the `.toc` etc., files.

For the purposes at hand it is generally impossible to treat the typesetting of a title and its number separately, as both are bundled into the ⟨*title*⟩ argument within `\contentsline`. They could be handled separately if the `\contentsline` command was suitably modified. If this was done, then the `\addcontentsline` command would also need to be changed which would then require the sectioning and captioning commands to be modified as well. This is certainly possible, but would cause problems if any other package also modified the sectioning or captioning commands, and there are several packages which do this.

Having said this, for all but Part entries, the sectional number is typeset via the `\numberline` command. We can take advantage of this fact.

I have taken the decision to not touch the `\contentsline` macro and instead to do what can be done with it as it exists. That is, I will modify the `\l@kind` commands. Essentially, my new definitions consist of inlined versions of the code for `\@dottedtocline`.

`\cftparfillskip` The `\l@kind` commands modify (locally) the value of `\parfillskip`. `\cftparfillskip` is a copy of the default *TEXbook* `\parfillskip` definition.

```
\newcommand{\cftparfillskip}{\parfillskip=0pt plus1fil}
```

(*End of definition for* `\cftparfillskip`*. This function is documented on page 12.*)

`\numberline` `\@cftinitnumwidth` The purpose of the `\numberline{`⟨*secnum*⟩`}` command is to typeset ⟨*secnum*⟩ left justified in a box of width `\@tempdima`. I redefine it to add three additional parameters, namely `\@cftbsnum`, `\@cftasnum` and `\@cftasnumb` (see `ltsect.dtx` for the original definition). `\@cftinitnumwidth` can be used to change `\@tempdima` based on the number e.g. in `\part`.

```
\newcommand\@cftinitnumwidth[1]{}
\renewcommand{\numberline}[1]{%
  \@cftinitnumwidth{#1}%
  \hb@xt@\@tempdima{%
  \UseHookWithArguments{contentsline/number/before}{1}{#1}%
  \@cftbsnum #1\@cftasnum\hfil
  \UseHookWithArguments{contentsline/number/after}{1}{#1}}%
  \@cftasnumb
  }
```

(*End of definition for* `\numberline` *and* `\@cftinitnumwidth`*. These functions are documented on page 4.*)

`\@cftbsnum` `\@cftasnum` `\@cftasnumb` Originally these were not defined but were `\let` to appropriate commands in the `\l@...` commands, but they have to be defined in case something unexpected calls `\numberline`, for example through use of the float package.[8]

```
\newcommand{\@cftbsnum}{}
\newcommand{\@cftasnum}{}
\newcommand{\@cftasnumb}{}
```

(*End of definition for* `\@cftbsnum`*,* `\@cftasnum`*, and* `\@cftasnumb`*. These functions are documented on page 17.*)

`\l@part` `\if@cftdopart` `\l@part{`⟨*title*⟩`}{`⟨*page*⟩`}` typesets the ToC entry for a `part` heading. It is a parameterised copy of the default `\l@part` (see `classes.dtx` for the original definition and the code below for `\l@subsection` for an explanation of most of this code). By default, Parts (and Chapters) do not have dotted leaders. This package provides for all entries to have dotted leaders.

```
\newif\if@cftdopart
\newif\if@cfthaspart
\@cftifundefined{part}{\@cfthaspartfalse}{\@cfthasparttrue}
\if@cfthaspart
\renewcommand*{\l@part}[2]{%
  \@cftdopartfalse
  \ifnum \c@tocdepth >-2\relax
    \if@cfthaschapter
      \@cftdoparttrue
```

[8] This bug was discovered by Andrew Thurber when using the tocloft and algorithm packages together.

```
    \fi
    \ifnum \c@tocdepth >\m@ne
      \if@cfthaschapter\else
        \@cftdoparttrue
      \fi
    \fi
  \fi
  \if@cftdopart
    \if@cfthaschapter
      \addpenalty{-\@highpenalty}%
    \else
      \addpenalty\@secpenalty
    \fi
    \addvspace{\cftbeforepartskip}%
    \begingroup
      {\leftskip \cftpartindent\relax
       \rightskip \@tocrmarg
       \parfillskip -\rightskip
       \parindent \cftpartindent\relax\@afterindenttrue
       \interlinepenalty\@M
       \leavevmode
       \@tempdima \cftpartnumwidth\relax
       \let\@cftinitnumwidth\cftpartinitnumwidth
       \let\@cftbsnum \cftpartpresnum
       \let\@cftasnum \cftpartaftersnum
       \let\@cftasnumb \cftpartaftersnumb
       \advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
```

In default LaTeX, the part ToC entry is written without `\numberline` and hence the 'presnum' needs to be inserted manually. In Koma-Script and titlesec (and probably others—let me know!), however, this is not the case.

```
       \UseHookWithArguments{contentsline/text/before}{4}
          {-1}{#1}{#2}{\@contentsline@destination}%
       {\cftpartfont \if@cftkoma\else\if@cfttitlesec\else\cftpartpresnum\fi\fi #1}%
       \UseHookWithArguments{contentsline/text/after}{4}
          {-1}{#1}{#2}{\@contentsline@destination}%
       \cftpartfillnum{#2}}
       \nobreak
       \if@cfthaschapter
         \global\@nobreaktrue
         \everypar{\global\@nobreakfalse\everypar{}}%
       \else
         \if@compatibility
           \global\@nobreaktrue
           \everypar{\global\@nobreakfalse\everypar{}}%
         \fi
       \fi
    \endgroup
  \fi}
\fi
```

(*End of definition for* `\l@part` *and* `\if@cftdopart`.)

`\cftbeforepartskip`
`\cftpartnumwidth`
`\cftpartfont`
`\cftpartpresnum`
`\cftpartaftersnum`
`\cftpartaftersnumb`
`\cftpartleader`
`\cftpartdotsep`
`\cftpartpagefont`
`\cftpartafterpnum`
`\cftpartpnumfinal`

These are the user commands to control the typesetting of Part entries. They are ini-

tialised to give the standard appearance.

```
\if@cfthaspart
  \newlength{\cftbeforepartskip}
    \setlength{\cftbeforepartskip}{2.25em \@plus\p@}
  \newlength{\cftpartnumwidth}
    \setlength{\cftpartnumwidth}{3em}
  \newcommand{\cftpartfont}{\large\bfseries}
  \newcommand{\cftpartinitnumwidth}[1]{\settowidth\@tempdima{#1}}
  \newcommand{\cftpartpresnum}{}
  \newcommand{\cftpartaftersnum}{}
  \newcommand{\cftpartaftersnumb}{\hspace{1em}}
  \newcommand{\cftpartleader}{\large\bfseries\cftdotfill{\cftpartdotsep}}
  \newcommand{\cftpartdotsep}{\cftnodots}
  \newcommand{\cftpartpagefont}{\large\bfseries}
  \newcommand{\cftpartafterpnum}{}
  \newcommand{\cftpartpnumfinal}{\cftpnumfinaldefault}
  \newlength{\cftpartindent}
    \setlength{\cftpartindent}{0em}
  \newcommand{\cftpartfillnum}[1]{%
    {%
     \UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
     \cftpartleader
     \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
    }%
    {\UseHookWithArguments{contentsline/page/before}{4}
       {-1}{}{#1}{\@contentsline@destination}%
     \makebox[\@pnumwidth][\cftpnumalign]{\cftpartpagefont #1}%
     \UseHookWithArguments{contentsline/page/after}{4}
       {-1}{}{#1}{\@contentsline@destination}%
     \cftpartafterpnum\cftpartpnumfinal\par}%
  }
```

koma classes use some different settings.

```
  \if@cftkoma
    \setlength{\cftpartnumwidth}{2em}
    \renewcommand{\cftpartfont}{\sectfont\large}
    \renewcommand{\cftpartpagefont}{\sectfont\large}
  \fi
\fi
```

(*End of definition for* `\cftbeforepartskip` *and others. These functions are documented on page 9.*)

`\l@chapter` `\l@chapter{`⟨*title*⟩`}{`⟨*page*⟩`}` typesets the ToC entry for a `chapter` heading. It is a parameterised copy of the default `\l@chapter` (see `classes.dtx` for the original definition). This only applies to chaptered documents.

```
\if@cfthaschapter
\renewcommand*{\l@chapter}[2]{%
  \ifnum \c@tocdepth >\m@ne
    \addpenalty{-\@highpenalty}%
    \vskip \cftbeforechapskip
    {\leftskip \cftchapindent\relax
     \rightskip \@tocrmarg
     \parfillskip -\rightskip
     \parindent \cftchapindent\relax\@afterindenttrue
```

```
      \interlinepenalty\@M
      \leavevmode
      \@tempdima \cftchapnumwidth\relax
      \let\@cftbsnum \cftchappresnum
      \let\@cftasnum \cftchapaftersnum
      \let\@cftasnumb \cftchapaftersnumb
      \advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
      \UseHookWithArguments{contentsline/text/before}{4}
          {0}{#1}{#2}{\@contentsline@destination}%
      {\cftchapfont #1}\nobreak
      \UseHookWithArguments{contentsline/text/after}{4}
          {0}{#1}{#2}{\@contentsline@destination}%
      \cftchapfillnum{#2}}%
  \fi}%
\fi
```

(*End of definition for* `\l@chapter`.)

`\cftbeforechapskip` `\cftchapindent` `\cftchapnumwidth` `\cftchapfont` `\cftchappresnum` `\cftchapaftersnum` `\cftchapaftersnumb` `\cftchapleader` `\cftchapdotsep` `\cftchappagefont` `\cftchapafterpnum` `\cftchappnumfinal` `\cftchapfillnum`

These are the user commands to control the typesetting of Chapter entries. They are initialised to give the standard appearance.

```
\if@cfthaschapter
  \newlength{\cftbeforechapskip}
    \setlength{\cftbeforechapskip}{1.0em \@plus\p@}
  \newlength{\cftchapindent}
    \setlength{\cftchapindent}{0em}
  \newlength{\cftchapnumwidth}
    \setlength{\cftchapnumwidth}{1.5em}
  \newcommand{\cftchapfont}{\bfseries}
  \newcommand{\cftchappresnum}{}
  \newcommand{\cftchapaftersnum}{}
  \newcommand{\cftchapaftersnumb}{}
  \newcommand{\cftchapleader}{\bfseries\cftdotfill{\cftchapdotsep}}
  \newcommand{\cftchapdotsep}{\cftnodots}
  \newcommand{\cftchappagefont}{\bfseries}
  \newcommand{\cftchapafterpnum}{}
  \newcommand{\cftchappnumfinal}{\cftpnumfinaldefault}
  \newcommand{\cftchapfillnum}[1]{%
    {\UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
     \cftchapleader
     \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
    }\nobreak
    \UseHookWithArguments{contentsline/page/before}{4}
       {0}{}{#1}{\@contentsline@destination}%
    \makebox[\@pnumwidth][\cftpnumalign]{\cftchappagefont #1}%
    \UseHookWithArguments{contentsline/page/after}{4}
       {0}{}{#1}{\@contentsline@destination}%
    \cftchapafterpnum\cftchappnumfinal\par
  }
```

koma classes have different chapter settings.

```
  \if@cftkoma
    \renewcommand{\cftchapfont}{\sectfont}
  \fi
\fi
```

(*End of definition for* `\cftbeforechapskip` *and others. These functions are documented on page 9.*)

`\l@section` `\l@section{`⟨*title*⟩`}{`⟨*page*⟩`}` typesets the ToC entry for a `section` heading. It is a parameterised copy of the default `\l@section` (see `classes.dtx` for the original definition).

```
\renewcommand*{\l@section}[2]{%
  \ifnum \c@tocdepth >\z@
    \if@cfthaschapter
      \vskip \cftbeforesecskip
    \else
      \addpenalty\@secpenalty
      \addvspace{\cftbeforesecskip}
    \fi
    {\leftskip \cftsecindent\relax
     \rightskip \@tocrmarg
     \parfillskip -\rightskip
     \parindent \cftsecindent\relax\@afterindenttrue
     \interlinepenalty\@M
     \leavevmode
     \@tempdima \cftsecnumwidth\relax
     \let\@cftbsnum \cftsecpresnum
     \let\@cftasnum \cftsecaftersnum
     \let\@cftasnumb \cftsecaftersnumb
     \advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
     \UseHookWithArguments{contentsline/text/before}{4}
       {1}{#1}{#2}{\@contentsline@destination}%
     {\cftsecfont #1}\nobreak
     \UseHookWithArguments{contentsline/text/after}{4}
       {1}{#1}{#2}{\@contentsline@destination}%
     \cftsecfillnum{#2}}%
  \fi}
```

(*End of definition for* `\l@section`.)

`\cftbeforesecskip` `\cftsecindent` `\cftsecnumwidth` `\cftsecfont` `\cftsecpresnum` `\cftsecaftersnum` `\cftsecaftersnumb` `\cftsecleader` `\cftsecdotsep` `\cftsecpagefont` `\cftsecafterpnum` `\cftsecpnumfinal` `\cftsecfillnum`

These are the user commands to control the typesetting of Section entries. They are initialised to give the standard appearance.

```
\newlength{\cftbeforesecskip}
\newlength{\cftsecindent}
\newlength{\cftsecnumwidth}
\newcommand{\cftsecpresnum}{}
\newcommand{\cftsecaftersnum}{}
\newcommand{\cftsecaftersnumb}{}
\if@cfthaschapter
  \setlength{\cftbeforesecskip}{\z@ \@plus.2\p@}
  \setlength{\cftsecindent}{1.5em}
  \setlength{\cftsecnumwidth}{2.3em}
  \newcommand{\cftsecfont}{\normalfont}
  \newcommand{\cftsecleader}{\normalfont\cftdotfill{\cftsecdotsep}}
  \newcommand{\cftsecdotsep}{\cftdotsep}
  \newcommand{\cftsecpagefont}{\normalfont}
\else
  \setlength{\cftbeforesecskip}{1.0em \@plus\p@}
  \setlength{\cftsecindent}{0em}
  \setlength{\cftsecnumwidth}{1.5em}
  \newcommand{\cftsecfont}{\bfseries}
```

```
  \newcommand{\cftsecleader}{\bfseries\cftdotfill{\cftsecdotsep}}
  \newcommand{\cftsecdotsep}{\cftnodots}
  \newcommand{\cftsecpagefont}{\bfseries}
\fi
\newcommand{\cftsecafterpnum}{}
\newcommand{\cftsecpnumfinal}{\cftpnumfinaldefault}
\newcommand{\cftsecfillnum}[1]{%
  {%
   \UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
   \cftsecleader
   \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
  }\nobreak
  \UseHookWithArguments{contentsline/page/before}{4}
    {1}{}{#1}{\@contentsline@destination}%
  \makebox[\@pnumwidth][\cftpnumalign]{\cftsecpagefont #1}%
  \UseHookWithArguments{contentsline/page/after}{4}
    {1}{}{#1}{\@contentsline@destination}%
    \cftsecafterpnum\cftsecpnumfinal\par
}
```

(*End of definition for* `\cftbeforesecskip` *and others. These functions are documented on page 9.*)

`\l@subsection` `\l@subsection{`⟨*title*⟩`}{`⟨*page*⟩`}` typesets the ToC entry for a `subsection` heading. It is a parameterised copy of the default `\l@subsection` (see `classes.dtx` for the original definition).

```
\renewcommand*{\l@subsection}[2]{%
```

Only typeset the entry if it falls within the `tocdepth`.

```
  \ifnum \c@tocdepth >\@ne
```

Add some vertical space.

```
    \vskip \cftbeforesubsecskip
```

Start a group to keep paragraphing changes local. Set the `\leftskip` to the entry's indentation.

```
    {\leftskip \cftsubsecindent\relax
```

Set the `\rightskip` to `\@tocrmarg` to leave room for the page number.

```
     \rightskip \@tocrmarg
```

Ensure that the last line of the entry will be filled. Setting `\parfillskip` to a negative number prevents any overfull box messages.

```
     \parfillskip -\rightskip
```

Set the paragraph indent to the entry's indentation.

```
     \parindent \cftsubsecindent\relax\@afterindenttrue
```

Try and prevent breaks between lines in a multiple line entry.

```
     \interlinepenalty\@M
```

Make sure that we have left vertical mode.

```
     \leavevmode
```

Our version of `\numberline` expects that the width of the number box is in `\@tempdima`, and that the three macros `\@cftbsnum`, `\@cftasnum` and `\@cftasnumb` are defined. We set all these to the values for this entry.

```
\@tempdima \cftsubsecnumwidth\relax
\let\@cftbsnum \cftsubsecpresnum
\let\@cftasnum \cftsubsecaftersnum
\let\@cftasnumb \cftsubsecaftersnumb
```

Arrange that the (section number and) first line of the title is set at the current indent, and any further lines are further indented.

```
\advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
```

Print the (number and) title, prohibiting any breaking.

```
\UseHookWithArguments{contentsline/text/before}{4}{2}{#1}{#2}{\@contentsline@destinatio
{\cftsubsecfont #1}\nobreak
\UseHookWithArguments{contentsline/text/after}{4}{2}{#1}{#2}{\@contentsline@destination
```

Print the leader and the page number, and close the group.

```
\cftsubsecfillnum{#2}}%
\fi}
```

(*End of definition for* `\l@subsection`.)

`\cftbeforesubsecskip` `\cftsubsecindent` `\cftsubsecnumwidth` `\cftsubsecfont` `\cftsubsecpresnum` `\cftsubsecaftersnum` `\cftsubsecaftersnumb` `\cftsubsecleader` `\cftsubsecdotsep` `\cftsubsecpagefont` `\cftsubsecafterpnum` `\cftsubsecpnumfinal`

These are the user commands to control the typesetting of Sub-section entries. They are initialised to give the standard appearance.

```
\newlength{\cftbeforesubsecskip}
  \setlength{\cftbeforesubsecskip}{\z@ \@plus.2\p@}
\newlength{\cftsubsecindent}
\newlength{\cftsubsecnumwidth}
\if@cfthaschapter
  \setlength{\cftsubsecindent}{3.8em}
  \setlength{\cftsubsecnumwidth}{3.2em}
\else
  \setlength{\cftsubsecindent}{1.5em}
  \setlength{\cftsubsecnumwidth}{2.3em}
\fi
\newcommand{\cftsubsecfont}{\normalfont}
\newcommand{\cftsubsecpresnum}{}
\newcommand{\cftsubsecaftersnum}{}
\newcommand{\cftsubsecaftersnumb}{}
\newcommand{\cftsubsecleader}{\normalfont\cftdotfill{\cftsubsecdotsep}}
\newcommand{\cftsubsecdotsep}{\cftdotsep}
\newcommand{\cftsubsecpagefont}{\normalfont}
\newcommand{\cftsubsecafterpnum}{}
\newcommand{\cftsubsecpnumfinal}{\cftpnumfinaldefault}
```

(*End of definition for* `\cftbeforesubsecskip` *and others. These functions are documented on page 9.*)

`\cftsubsecfillnum`

`\cftsubsecfillnum{`⟨*page*⟩`}` typesets the leader and the ⟨*page*⟩ number of a `subsection` entry. First print the leader and then, with no break, set the page number flushright in a box of width `\@pnumwidth`, not forgetting to finish the paragraph.

```
\newcommand{\cftsubsecfillnum}[1]{%
  {%
   \UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
```

```
    \cftsubsecleader
    \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
  }\nobreak
  \UseHookWithArguments{contentsline/page/before}{4}
    {2}{}{#1}{\@contentsline@destination}%
  \makebox[\@pnumwidth][\cftpnumalign]{\cftsubsecpagefont #1}%
  \UseHookWithArguments{contentsline/page/after}{4}
    {2}{}{#1}{\@contentsline@destination}%
    \cftsubsecafterpnum\cftsubsecpnumfinal\par
}
```

(*End of definition for* `\cftsubsecfillnum`. *This function is documented on page 10.*)

`\l@subsubsection`

`\l@subsubsection{`⟨*title*⟩`}{`⟨*page*⟩`}` typesets the ToC entry for a `subsubsection` heading. It is a parameterised copy of the default `\l@subsubsection` (see `classes.dtx` for the original definition).

```
\renewcommand*{\l@subsubsection}[2]{%
  \ifnum \c@tocdepth >\tw@
    \vskip \cftbeforesubsubsecskip
    {\leftskip \cftsubsubsecindent\relax
     \rightskip \@tocrmarg
     \parfillskip -\rightskip
     \parindent \cftsubsubsecindent\relax\@afterindenttrue
     \interlinepenalty\@M
     \leavevmode
     \@tempdima \cftsubsubsecnumwidth\relax
     \let\@cftbsnum \cftsubsubsecpresnum
     \let\@cftasnum \cftsubsubsecaftersnum
     \let\@cftasnumb \cftsubsubsecaftersnumb
     \advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
     \UseHookWithArguments{contentsline/text/before}{4}{3}{#1}{#2}{\@contentsline@destinatio
     {\cftsubsubsecfont #1}\nobreak
     \UseHookWithArguments{contentsline/text/after}{4}{3}{#1}{#2}{\@contentsline@destination
     \cftsubsubsecfillnum{#2}}%
  \fi}
```

(*End of definition for* `\l@subsubsection`.)

`\cftbeforesubsubsecskip`
`\cftsubsubsecindent`
`\cftsubsubsecnumwidth`
`\cftsubsubsecfont`
`\cftsubsubsecpresnum`
`\cftsubsubsecaftersnum`
`\cftsubsubsecaftersnumb`
`\cftsubsubsecleader`
`\cftsubsubsecdotsep`
`\cftsubsubsecpagefont`
`\cftsubsubsecafterpnum`
`\cftsubsubsecpnumfinal`
`\cftsubsubsecfillnum`

These are the user commands to control the typesetting of Sub-sub-section entries. They are initialised to give the standard appearance.

```
\newlength{\cftbeforesubsubsecskip}
  \setlength{\cftbeforesubsubsecskip}{\z@ \@plus.2\p@}
\newlength{\cftsubsubsecindent}
\newlength{\cftsubsubsecnumwidth}
\if@cfthaschapter
  \setlength{\cftsubsubsecindent}{7.0em}
  \setlength{\cftsubsubsecnumwidth}{4.1em}
\else
  \setlength{\cftsubsubsecindent}{3.8em}
  \setlength{\cftsubsubsecnumwidth}{3.2em}
\fi
\newcommand{\cftsubsubsecfont}{\normalfont}
\newcommand{\cftsubsubsecpresnum}{}
\newcommand{\cftsubsubsecaftersnum}{}
```

```
\newcommand{\cftsubsubsecaftersnumb}{}
\newcommand{\cftsubsubsecleader}{\normalfont\cftdotfill{\cftsubsubsecdotsep}}
\newcommand{\cftsubsubsecdotsep}{\cftdotsep}
\newcommand{\cftsubsubsecpagefont}{\normalfont}
\newcommand{\cftsubsubsecafterpnum}{}
\newcommand{\cftsubsubsecpnumfinal}{\cftpnumfinaldefault}
\newcommand{\cftsubsubsecfillnum}[1]{%
  {%
   \UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
   \cftsubsubsecleader
   \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
  }\nobreak
  \UseHookWithArguments{contentsline/page/before}{4}
    {3}{}{#1}{\@contentsline@destination}%
  \makebox[\@pnumwidth][\cftpnumalign]{\cftsubsubsecpagefont #1}%
  \UseHookWithArguments{contentsline/page/after}{4}
    {3}{}{#1}{\@contentsline@destination}%
    \cftsubsubsecafterpnum\cftsubsubsecpnumfinal\par
}
```

(*End of definition for* `\cftbeforesubsubsecskip` *and others. These functions are documented on page 9.*)

`\l@paragraph` `\l@paragraph{`⟨*title*⟩`}{`⟨*page*⟩`}` typesets the ToC entry for a `paragraph` heading. It is a parameterised copy of the default `\l@paragraph` (see `classes.dtx` for the original definition).

```
\renewcommand*{\l@paragraph}[2]{%
  \ifnum \c@tocdepth >3\relax
    \vskip \cftbeforeparaskip
    {\leftskip \cftparaindent\relax
     \rightskip \@tocrmarg
     \parfillskip -\rightskip
     \parindent \cftparaindent\relax\@afterindenttrue
     \interlinepenalty\@M
     \leavevmode
     \@tempdima \cftparanumwidth\relax
     \let\@cftbsnum \cftparapresnum
     \let\@cftasnum \cftparaaftersnum
     \let\@cftasnumb \cftparaaftersnumb
     \advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
     \UseHookWithArguments{contentsline/text/before}{4}
       {4}{#1}{#2}{\@contentsline@destination}%
     {\cftparafont #1}\nobreak
     \UseHookWithArguments{contentsline/text/after}{4}
       {4}{#1}{#2}{\@contentsline@destination}%
     \cftparafillnum{#2}}%
  \fi}
```

(*End of definition for* `\l@paragraph`.)

`\cftbeforeparaskip` `\cftparaindent` `\cftparanumwidth` `\cftparafont` `\cftparapresnum` `\cftparaaftersnum` `\cftparaaftersnumb` `\cftparaleader` `\cftparadotsep` `\cftparapagefont` `\cftparaafterpnum` `\cftparapnumfinal` `\cftparafillnum`

These are the user commands to control the typesetting of Paragraph entries. They are initialised to give the standard appearance.

```
\newlength{\cftbeforeparaskip}
  \setlength{\cftbeforeparaskip}{\z@ \@plus.2\p@}
\newlength{\cftparaindent}
```

```
\newlength{\cftparanumwidth}
\if@cfthaschapter
  \setlength{\cftparaindent}{10em}
  \setlength{\cftparanumwidth}{5em}
\else
  \setlength{\cftparaindent}{7.0em}
  \setlength{\cftparanumwidth}{4.1em}
\fi
\newcommand{\cftparafont}{\normalfont}
\newcommand{\cftparapresnum}{}
\newcommand{\cftparaaftersnum}{}
\newcommand{\cftparaaftersnumb}{}
\newcommand{\cftparaleader}{\normalfont\cftdotfill{\cftparadotsep}}
\newcommand{\cftparadotsep}{\cftdotsep}
\newcommand{\cftparapagefont}{\normalfont}
\newcommand{\cftparaafterpnum}{}
\newcommand{\cftparapnumfinal}{\cftpnumfinaldefault}
\newcommand{\cftparafillnum}[1]{%
  {%
   \UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
   \cftparaleader
   \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
  }\nobreak
  \UseHookWithArguments{contentsline/page/before}{4}
    {4}{}{#1}{\@contentsline@destination}%
  \makebox[\@pnumwidth][\cftpnumalign]{\cftparapagefont #1}%
  \UseHookWithArguments{contentsline/page/after}{4}
    {4}{}{#1}{\@contentsline@destination}%
    \cftparaafterpnum\cftparapnumfinal\par
}
```

(*End of definition for* `\cftbeforeparaskip` *and others. These functions are documented on page 9.*)

`\l@subparagraph` `\l@subparagraph{`⟨*title*⟩`}{`⟨*page*⟩`}` typesets the ToC entry for a `subparagraph` heading. It is a parameterised copy of the default `\l@subparagraph` (see `classes.dtx` for the original definition).

```
\renewcommand*{\l@subparagraph}[2]{%
  \ifnum \c@tocdepth >4\relax
    \vskip \cftbeforesubparaskip
    {\leftskip \cftsubparaindent\relax
     \rightskip \@tocrmarg
     \parfillskip -\rightskip
     \parindent \cftsubparaindent\relax\@afterindenttrue
     \interlinepenalty\@M
     \leavevmode
     \@tempdima \cftsubparanumwidth\relax
     \let\@cftbsnum \cftsubparapresnum
     \let\@cftasnum \cftsubparaaftersnum
     \let\@cftasnumb \cftsubparaaftersnumb
     \advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
     \UseHookWithArguments{contentsline/text/before}{4}
       {5}{#1}{#2}{\@contentsline@destination}%
     {\cftsubparafont #1}\nobreak
     \UseHookWithArguments{contentsline/text/after}{4}
```

```
        {5}{#1}{#2}{\@contentsline@destination}%
      \cftsubparafillnum{#2}}%
  \fi}
```

(*End of definition for* `\l@subparagraph`.)

`\cftbeforesubparaskip` `\cftsubparaindent` `\cftsubparanumwidth` `\cftsubparafont` `\cftsubparapresnum` `\cftsubparaaftersnum` `\cftsubparaaftersnumb` `\cftsubparaleader` `\cftsubparadotsep` `\cftsubparapagefont` `\cftsubparaafterpnum` `\cftsubparapnumfinal` `\cftsubparafillnum`

These are the user commands to control the typesetting of Sub-paragraph entries. They are initialised to give the standard appearance.

```
\newlength{\cftbeforesubparaskip}
  \setlength{\cftbeforesubparaskip}{\z@ \@plus.2\p@}
\newlength{\cftsubparaindent}
\newlength{\cftsubparanumwidth}
\if@cfthaschapter
  \setlength{\cftsubparaindent}{12em}
  \setlength{\cftsubparanumwidth}{6em}
\else
  \setlength{\cftsubparaindent}{10em}
  \setlength{\cftsubparanumwidth}{5em}
\fi
\newcommand{\cftsubparafont}{\normalfont}
\newcommand{\cftsubparapresnum}{}
\newcommand{\cftsubparaaftersnum}{}
\newcommand{\cftsubparaaftersnumb}{}
\newcommand{\cftsubparaleader}{\normalfont\cftdotfill{\cftsubparadotsep}}
\newcommand{\cftsubparadotsep}{\cftdotsep}
\newcommand{\cftsubparapagefont}{\normalfont}
\newcommand{\cftsubparaafterpnum}{}
\newcommand{\cftsubparapnumfinal}{\cftpnumfinaldefault}
\newcommand{\cftsubparafillnum}[1]{%
  {%
   \UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
   \cftsubparaleader
   \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
  }\nobreak
  \UseHookWithArguments{contentsline/page/before}{4}
    {5}{}{#1}{\@contentsline@destination}%
  \makebox[\@pnumwidth][\cftpnumalign]{\cftsubparapagefont #1}%
  \UseHookWithArguments{contentsline/page/after}{4}
    {5}{}{#1}{\@contentsline@destination}%
    \cftsubparaafterpnum\cftsubparapnumfinal\par
}
```

(*End of definition for* `\cftbeforesubparaskip` *and others. These functions are documented on page* 9.)

`\@cftdobiblof`

If the tocbibind package has been used and it has redefined `\listoffigures` we need to cater for that. The contents of the definition are defined in tocbibind.

```
\newcommand{\@cftdobiblof}{%
  \if@dotoclof
    \if@bibchapter
      \phantomsection
      \addcontentsline{toc}{chapter}{\cftloftitlename}
    \else
      \phantomsection
      \addcontentsline{toc}{\@tocextra}{\cftloftitlename}
    \fi
```

```
  \fi}
```

(*End of definition for* `\@cftdobiblof`.)

`\listoffigures` This is a parameterised version of the default `\listoffigures` command. The changes are postponed until after all packages have been loaded. Each class has its own definition, but we have to cater for all classes in one definition, hence some of the checks. First, perform the default checks for multicolumns. (Do nothing if titles option is used).

```
\AtBeginDocument{%
\if@cftnctoc\else
\renewcommand{\listoffigures}{%
  \@cfttocstart
```

Ensure that any previous paragraph has been finished. Within a group set the local paragraphing style. Typeset the title and then do the contents of the `.lof` file.

```
  \par
  \begingroup
    \parindent\z@ \parskip\cftparskip
    \@cftmakeloftitle
    \if@cfttocbibind
      \@cftdobiblof
    \fi
    \@starttoc{lof}%
  \endgroup
```

Finally, restore any multicolumn typesetting.

```
  \@cfttocfinish}%
\fi
}

```

(*End of definition for* `\listoffigures`. *This function is documented on page 7.*)

`\@cftmakeloftitle` This command typesets the title for the LoF.

```
\newcommand{\@cftmakeloftitle}{\cfttitlecommand{lof}}%
```

(*End of definition for* `\@cftmakeloftitle`.)

`\cftbeforeloftitleskip` `\cftafterloftitleskip` These two lengths control the vertical spacing before and after the LoF title.

```
\newlength{\cftbeforeloftitleskip}
\newlength{\cftafterloftitleskip}
```

Their values depend on whether the document has chapters or not. In chaptered documents the default LoF title is typeset as a `\chapter*`, otherwise as a `\section*`.

```
\if@cfthaschapter
  \setlength{\cftbeforeloftitleskip}{50pt}
  \setlength{\cftafterloftitleskip}{40pt}
\else
  \setlength{\cftbeforeloftitleskip}{3.5ex \@plus 1ex \@minus .2ex}
  \setlength{\cftafterloftitleskip}{2.3ex \@plus.2ex}
\fi
```

(*End of definition for* `\cftbeforeloftitleskip` *and* `\cftafterloftitleskip`. *These functions are documented on page 7.*)

\cftloftitlefont
\cftafterloftitle

The LoF title is typeset in the style given by `\cftloftitlefont`. The macro `\cftafterloftitle` is called after typesetting the title. This is initialised to do nothing. Both these macros can be redefined to do other things (e.g., adding an `\hfill` to `\cftloftitlefont` will make the title flushright).

```
\if@cfthaschapter
  \newcommand{\cftloftitlefont}{\normalfont\Huge\bfseries}
  \if@cftkoma\renewcommand{\cftloftitlefont}{\size@chapter\sectfont}\fi
\else
  \newcommand{\cftloftitlefont}{\normalfont\Large\bfseries}
  \if@cftkoma\renewcommand{\cftloftitlefont}{\size@section\sectfont}\fi
\fi
\newcommand{\cftafterloftitle}{}

```

(*End of definition for* `\cftloftitlefont` *and* `\cftafterloftitle`*. These functions are documented on page 8.*)

\l@figure

`\l@figure{`⟨*title*⟩`}{`⟨*page*⟩`}` typesets the LoF entry for a `figure` caption heading. It is a parameterised copy of the default `\l@figure` (see `classes.dtx` for the original definition).

```
\renewcommand*{\l@figure}[2]{%
  \ifnum \c@lofdepth >\z@
    \vskip \cftbeforefigskip
    {\leftskip \cftfigindent\relax
     \rightskip \@tocrmarg
     \parfillskip -\rightskip
     \parindent \cftfigindent\relax\@afterindenttrue
     \interlinepenalty\@M
     \leavevmode
     \@tempdima \cftfignumwidth\relax
     \let\@cftbsnum \cftfigpresnum
     \let\@cftasnum \cftfigaftersnum
     \let\@cftasnumb \cftfigaftersnumb
     \advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
     \UseHookWithArguments{contentsline/text/before}{4}
       {1}{#1}{#2}{\@contentsline@destination}%
     {\cftfigfont #1}\nobreak
     \UseHookWithArguments{contentsline/text/after}{4}
       {1}{#1}{#2}{\@contentsline@destination}%
     \cftfigfillnum{#2}}%
   \fi
  }
```

(*End of definition for* `\l@figure`*.*)

\cftbeforefigskip
\cftfigindent
\cftfignumwidth
\cftfigfont
\cftfigpresnum
\cftfigaftersnum
\cftfigaftersnumb
\cftfigleader
\cftfigdotsep
\cftfigpagefont
\cftfigafterpnum
\cftfigpnumfinal
\cftfigfillnum

These are the user commands to control the typesetting of Figure caption entries. They are initialised to give the standard appearance.

```
\newlength{\cftbeforefigskip}
  \setlength{\cftbeforefigskip}{\z@ \@plus.2\p@}
\newlength{\cftfigindent}
  \setlength{\cftfigindent}{1.5em}
\newlength{\cftfignumwidth}
  \setlength{\cftfignumwidth}{2.3em}
\newcommand{\cftfigfont}{\normalfont}
```

```
\newcommand{\cftfigpresnum}{}
\newcommand{\cftfigaftersnum}{}
\newcommand{\cftfigaftersnumb}{}
\newcommand{\cftfigleader}{\normalfont\cftdotfill{\cftfigdotsep}}
\newcommand{\cftfigdotsep}{\cftdotsep}
\newcommand{\cftfigpagefont}{\normalfont}
\newcommand{\cftfigafterpnum}{}
\newcommand{\cftfigpnumfinal}{\cftpnumfinaldefault}
\newcommand{\cftfigfillnum}[1]{%
  {%
   \UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
   \cftfigleader
   \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
  }\nobreak
  \UseHookWithArguments{contentsline/page/before}{4}
    {1}{}{#1}{\@contentsline@destination}%
  \makebox[\@pnumwidth][\cftpnumalign]{\cftfigpagefont #1}%
  \UseHookWithArguments{contentsline/page/after}{4}
    {1}{}{#1}{\@contentsline@destination}%
    \cftfigafterpnum\cftfigpnumfinal\par
}
```

(*End of definition for* `\cftbeforefigskip` *and others. These functions are documented on page 9.*)

`lofdepth` `lotdepth`

The counters `lofdepth` and `lotdepth` are defined by the subfigure package. Define them here if that package is not used.

```
\if@cftsubfigopt\else
  \newcounter{lofdepth}\setcounter{lofdepth}{1}
  \newcounter{lotdepth}\setcounter{lotdepth}{1}
\fi

```

(*End of definition for* `lofdepth` *and* `lotdepth`*. These functions are documented on page 8.*)

`\@cftdobiblot`

If the tocbibind package has been used and it has redefined `\listoftables` we need to cater for that. The contents of the definition are defined in tocbibind.

```
\newcommand{\@cftdobiblot}{%
  \if@dotoclot
    \if@bibchapter
      \phantomsection
      \addcontentsline{toc}{chapter}{\cftlottitlename}
    \else
      \phantomsection
      \addcontentsline{toc}{\@tocextra}{\cftlottitlename}
    \fi
  \fi}

```

(*End of definition for* `\@cftdobiblot`.)

`\listoftables`

This is a parameterised version of the default `\listoftables` command. The changes are postponed until after all packages have been loaded. Each class has its own definition, but we have to cater for all classes in one definition, hence some of the checks. First,

perform the default checks for multicolumns. (Do nothing if the titles option has been used).

```
\AtBeginDocument{%
\if@cftnctoc\else
\renewcommand{\listoftables}{%
  \@cfttocstart
```

Ensure that any previous paragraph has been finished. Within a group set the local paragraphing style. Typeset the title and then do the contents of the `.lot` file.

```
  \par
  \begingroup
    \parindent\z@ \parskip\cftparskip
    \@cftmakelottitle
    \if@cfttocbibind
      \@cftdobiblot
    \fi
    \@starttoc{lot}%
  \endgroup
```

Finally, restore any multicolumn typesetting.

```
  \@cfttocfinish}%
\fi
}
```

(*End of definition for* `\listoftables`. *This function is documented on page 7.*)

`\@cftmakelottitle` This command typesets the title for the LoT.

```
\newcommand{\@cftmakelottitle}{\cfttitlecommand{lot}}%
```

(*End of definition for* `\@cftmakelottitle`.)

`\cftbeforelottitleskip` `\cftafterlottitleskip` These two lengths control the vertical spacing before and after the LoT title.

```
\newlength{\cftbeforelottitleskip}
\newlength{\cftafterlottitleskip}
```

Their values depend on whether the document has chapters or not. In chaptered documents the default LoT title is typeset as a `\chapter*`, otherwise as a `\section*`.

```
\if@cfthaschapter
  \setlength{\cftbeforelottitleskip}{50pt}
  \setlength{\cftafterlottitleskip}{40pt}
\else
  \setlength{\cftbeforelottitleskip}{3.5ex \@plus 1ex \@minus .2ex}
  \setlength{\cftafterlottitleskip}{2.3ex \@plus.2ex}
\fi
```

(*End of definition for* `\cftbeforelottitleskip` *and* `\cftafterlottitleskip`. *These functions are documented on page 7.*)

`\cftlottitlefont` `\cftafterlottitle` The LoT title is typeset in the style given by `\cftlottitlefont`. The macro `\cftafterlottitle` is called after typesetting the title. This is initialised to do nothing. Both these macros can be redefined to do other things (e.g., adding an `\hfill` to `\cftlottitlefont` will make the title flushright).

```
\if@cfthaschapter
```

```
  \newcommand{\cftlottitlefont}{\normalfont\Huge\bfseries}
  \if@cftkoma\renewcommand{\cftlottitlefont}{\size@chapter\sectfont}\fi
\else
  \newcommand{\cftlottitlefont}{\normalfont\Large\bfseries}
  \if@cftkoma\renewcommand{\cftlottitlefont}{\size@section\sectfont}\fi
\fi
\newcommand{\cftafterlottitle}{}

```

(*End of definition for* `\cftlottitlefont` *and* `\cftafterlottitle`*. These functions are documented on page 8.*)

`\l@table` `\l@table{`⟨*title*⟩`}{`⟨*page*⟩`}` typesets the LoT entry for a `table` caption heading. It is a parameterised copy of the default `\l@table` (see `classes.dtx` for the original definition).

```
\renewcommand*{\l@table}[2]{%
  \ifnum\c@lotdepth >\z@
    \vskip \cftbeforetabskip
    {\leftskip \cfttabindent\relax
     \rightskip \@tocrmarg
     \parfillskip -\rightskip
     \parindent \cfttabindent\relax\@afterindenttrue
     \interlinepenalty\@M
     \leavevmode
     \@tempdima \cfttabnumwidth\relax
     \let\@cftbsnum \cfttabpresnum
     \let\@cftasnum \cfttabaftersnum
     \let\@cftasnumb \cfttabaftersnumb
     \advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
     \UseHookWithArguments{contentsline/text/before}{4}
       {1}{#1}{#2}{\@contentsline@destination}%
      {\cfttabfont #1}\nobreak
     \UseHookWithArguments{contentsline/text/after}{4}
       {1}{#1}{#2}{\@contentsline@destination}%
     \cfttabfillnum{#2}}%
   \fi
  }
```

(*End of definition for* `\l@table`*.*)

`\cftbeforetabskip` `\cfttabindent` `\cfttabnumwidth` `\cfttabfont` `\cfttabpresnum` `\cfttabaftersnum` `\cfttabaftersnumb` `\cfttableader` `\cfttabdotsep` `\cfttabpagefont` `\cfttabafterpnum` `\cfttabpnumfinal` `\cfttabfillnum`

These are the user commands to control the typesetting of Table caption entries. They are initialised to give the standard appearance.

```
\newlength{\cftbeforetabskip}
  \setlength{\cftbeforetabskip}{\z@ \@plus.2\p@}
\newlength{\cfttabindent}
  \setlength{\cfttabindent}{1.5em}
\newlength{\cfttabnumwidth}
  \setlength{\cfttabnumwidth}{2.3em}
\newcommand{\cfttabfont}{\normalfont}
\newcommand{\cfttabpresnum}{}
\newcommand{\cfttabaftersnum}{}
\newcommand{\cfttabaftersnumb}{}
\newcommand{\cfttableader}{\normalfont\cftdotfill{\cfttabdotsep}}
\newcommand{\cfttabdotsep}{\cftdotsep}
\newcommand{\cfttabpagefont}{\normalfont}
\newcommand{\cfttabafterpnum}{}
```

```
\newcommand{\cfttabpnumfinal}{\cftpnumfinaldefault}
\newcommand{\cfttabfillnum}[1]{%
  {%
   \UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
   \cfttableader
   \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
  }\nobreak
  \UseHookWithArguments{contentsline/page/before}{4}
    {1}{}{#1}{\@contentsline@destination}%
  \makebox[\@pnumwidth][\cftpnumalign]{\cfttabpagefont #1}%
  \UseHookWithArguments{contentsline/page/after}{4}
    {1}{}{#1}{\@contentsline@destination}%
    \cfttabafterpnum\cfttabpnumfinal\par
}
```

(*End of definition for* `\cftbeforetabskip` *and others. These functions are documented on page 9.*)

3.1 Support for the subfigure package

The code for supporting the subfigure package is, in all essentials, the same as that for the figure and table captions; only the names are changed. However, the code need only be executed if the subfigure package is actually loaded.

`\@cftl@subfig` This command redefines the `\l@subfigure` command.

```
\newcommand{\@cftl@subfig}{%
```

`\l@subfigure` `\l@subfigure{`⟨*title*⟩`}{`⟨*page*⟩`}` typesets the LoF entry for a `subfigure` caption heading. It is essentially the same as the parameterised code for `\l@figure` except that account has to be taken of `lofdepth`.

```
\renewcommand*{\l@subfigure}[2]{%
  \ifnum \toclevel@subfigure > \c@lofdepth
  \else
    \vskip \cftbeforesubfigskip
    {\leftskip \cftsubfigindent\relax
     \rightskip \@tocrmarg
     \parfillskip -\rightskip
     \parindent \cftsubfigindent\relax\@afterindenttrue
     \interlinepenalty\@M
     \leavevmode
     \@tempdima \cftsubfignumwidth\relax
     \let\@cftbsnum \cftsubfigpresnum
     \let\@cftasnum \cftsubfigaftersnum
     \let\@cftasnumb \cftsubfigaftersnumb
     \advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
     \UseHookWithArguments{contentsline/text/before}{4}
       {\toclevel@subfigure}{##1}{##2}{\@contentsline@destination}%
     {\cftsubfigfont ##1}\nobreak
     \UseHookWithArguments{contentsline/text/after}{4}
       {\toclevel@subfigure}{##1}{##2}{\@contentsline@destination}%
     \cftsubfigfillnum{##2}}%
  \fi
  }%
}

```

(*End of definition for* `\@cftl@subfig` *and* `\l@subfigure`.)

`\@cftsetsubfig` This command initialises the setup for subfigure captions in the LoF.

```
\newcommand{\@cftsetsubfig}{%
```

`\cftbeforesubfigskip`
`\cftsubfigindent`
`\cftsubfignumwidth`
`\cftsubfigfont`
`\cftsubfigpresnum`
`\cftsubfigaftersnum`
`\cftsubfigaftersnumb`
`\cftsubfigleader`
`\cftsubfigdotsep`
`\cftsubfigpagefont`
`\cftsubfigafterpnum`
`\cftsubfigpnumfinal`
`\toclevel@subfig`
`\cftsubfigfillnum`

```
\newlength{\cftbeforesubfigskip}
  \setlength{\cftbeforesubfigskip}{\z@ \@plus.2\p@}
\newlength{\cftsubfigindent}
  \setlength{\cftsubfigindent}{3.8em}
\newlength{\cftsubfignumwidth}
  \setlength{\cftsubfignumwidth}{2.5em}
\newcommand{\cftsubfigfont}{\normalfont}
\newcommand{\cftsubfigpresnum}{}
\newcommand{\cftsubfigaftersnum}{}
\newcommand{\cftsubfigaftersnumb}{}
\newcommand{\cftsubfigleader}{\normalfont\cftdotfill{\cftsubtabdotsep}}
\newcommand{\cftsubfigdotsep}{\cftdotsep}
\newcommand{\cftsubfigpagefont}{\normalfont}
\newcommand{\cftsubfigafterpnum}{}
\newcommand{\cftsubfigpnumfinal}{\cftpnumfinaldefault}
\providecommand{\toclevel@subfigure}{1}
\newcommand{\cftsubfigfillnum}[1]{%
  {%
   \UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
   \cftsubfigleader
   \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
  }\nobreak
  \UseHookWithArguments{contentsline/page/before}{4}
    {\toclevel@subfigure}{}{##1}{\@contentsline@destination}%
  \makebox[\@pnumwidth][\cftpnumalign]{\cftsubfigpagefont ##1}%
  \UseHookWithArguments{contentsline/page/after}{4}
    {\toclevel@subfigure}{}{##1}{\@contentsline@destination}%
    \cftsubfigafterpnum\cftsubfigpnumfinal\par
}
```

This is the end of `\@cftsetsubfig`.

```
}

```

(*End of definition for* `\@cftsetsubfig` *and others.*)

`\@cftl@subtab` This code redefines the code for `\l@subtable`.

```
\newcommand{\@cftl@subtab}{%
```

`\l@subtable` `\l@subtable{`⟨*title*⟩`}{`⟨*page*⟩`}` typesets the LoT entry for a `subtable` caption heading. It is essentially the same as the parameterised code for `\l@table` except account has to be taken of `lotdepth`.

```
\renewcommand*{\l@subtable}[2]{%
  \ifnum \toclevel@subtable > \c@lofdepth
  \else
    \vskip \cftbeforesubtabskip
    {\leftskip \cftsubtabindent\relax
     \rightskip \@tocrmarg
```

```
      \parfillskip -\rightskip
      \parindent \cftsubtabindent\relax\@afterindenttrue
      \interlinepenalty\@M
      \leavevmode
      \@tempdima \cftsubtabnumwidth\relax
      \let\@cftbsnum \cftsubtabpresnum
      \let\@cftasnum \cftsubtabaftersnum
      \let\@cftasnumb \cftsubtabaftersnumb
      \advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
      \UseHookWithArguments{contentsline/text/before}{4}
        {\toclevel@subtable}{##1}{##2}{\@contentsline@destination}%
      {\cftsubtabfont ##1}\nobreak
      \UseHookWithArguments{contentsline/text/after}{4}
        {\toclevel@subtable}{##1}{##2}{\@contentsline@destination}%
      \cftsubtabfillnum{##2}}%
  \fi
  }%
}
```

(*End of definition for* `\@cftl@subtab` *and* `\l@subtable`.)

`\@cftsetsubtab` This command sets up the defaults for subtable entries in the LoT.

```
\newcommand{\@cftsetsubtab}{%
```

These are the user commands to control the typesetting of Subtable caption entries. They are initialised to give the standard appearance.

`\cftbeforesubtabskip`
`\cftsubtabindent`
`\cftsubtabnumwidth`
`\cftsubtabfont`
`\cftsubtabpresnum`
`\cftsubtabaftersnum`
`\cftsubtabaftersnumb`
`\cftsubtableader`
`\cftsubtabdotsep`
`\cftsubtabpagefont`
`\cftsubtabafterpnum`
`\cftsubtabpnumfinal`
`\toclevel@subtable`
`\cftsubtabfillnum`

```
\newlength{\cftbeforesubtabskip}
  \setlength{\cftbeforesubtabskip}{\z@ \@plus.2\p@}
\newlength{\cftsubtabindent}
  \setlength{\cftsubtabindent}{3.8em}
\newlength{\cftsubtabnumwidth}
  \setlength{\cftsubtabnumwidth}{2.5em}
\newcommand{\cftsubtabfont}{\normalfont}
\newcommand{\cftsubtabpresnum}{}
\newcommand{\cftsubtabaftersnum}{}
\newcommand{\cftsubtabaftersnumb}{}
\newcommand{\cftsubtableader}{\normalfont\cftdotfill{\cftsubtabdotsep}}
\newcommand{\cftsubtabdotsep}{\cftdotsep}
\newcommand{\cftsubtabpagefont}{\normalfont}
\newcommand{\cftsubtabafterpnum}{}
\newcommand{\cftsubtabpnumfinal}{\cftpnumfinaldefault}
\providecommand{\toclevel@subtable}{1}
\newcommand{\cftsubtagfillnum}[1]{%
  {%
   \UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
   \cftsubtagleader
   \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
  }\nobreak
  \UseHookWithArguments{contentsline/page/before}{4}
    {\toclevel@subtable}{}{##1}{\@contentsline@destination}%
  \makebox[\@pnumwidth][\cftpnumalign]{\cftsubtagpagefont ##1}%
  \UseHookWithArguments{contentsline/page/after}{4}
    {\toclevel@subtable}{}{##1}{\@contentsline@destination}%
    \cftsubtagafterpnum\cftsubtagpnumfinal\par
}
```

This is the end of \@cftsetsubtab.

```
}
```

(*End of definition for* \@cftsetsubtab *and others.*)

Call the subfigure package setup code only if the subfigure option is specified. The \l@... redefinitions have to come after the subfigure package is loaded.

```
\if@cftsubfigopt
  \@cftsetsubfig\@cftsetsubtab
  \AtBeginDocument{\@cftl@subfig\@cftl@subtab}
\fi
%%  \AtBeginDocument{\if@cftsubfigopt
%%    \@cftsetsubfig\@cftsetsubtab
%%    \@cftl@subfig\@cftl@subtab
%%  \fi}
```

3.2 New list of...

\newlistentry

\newlistentry[⟨*within*⟩]{⟨*counter*⟩}{⟨*ext*⟩}{⟨*level-1*⟩} creates a set of commands for a new kind of entry into a List of.

```
\newcommand{\newlistentry}[4][\@empty]{%
```

Check if ⟨*within*⟩ and ⟨*counter*⟩ have been defined. It is an error if ⟨*within*⟩ has not been defined, and an error if ⟨*counter*⟩ has been defined. Set the default counter values.

\c@X
\theX

```
  \@ifundefined{c@#2}{%    check & set the counter
    \ifx \@empty#1\relax
      \newcounter{#2}
    \else
      \@ifundefined{c@#1}{\PackageWarning{tocloft}%
                          {#1 has no counter for use as a `within'}
        \newcounter{#2}}%
      {\newcounter{#2}[#1]%
       \expandafter\edef\csname the#2\endcsname{%
         \expandafter\noexpand\csname the#1\endcsname.\noexpand\arabic{#2}}}
    \fi
    \setcounter{#2}{0}
  }
  {\PackageError{tocloft}{#2 has been previously defined}{\@eha}}
```

That finishes off the error checking. No matter what the result, the rest of the new commands are defined.
\l@X{⟨*title*⟩}{⟨*page*⟩} typesets the entry.

\l@X

```
  \@namedef{l@#2}##1##2{%
```

Only typeset if the \Zdepth is greater than ⟨*level-1*⟩.

```
    \ifnum \@nameuse{c@#3depth} > #4\relax
      \vskip \@nameuse{cftbefore#2skip}
      {\leftskip \@nameuse{cft#2indent}\relax
       \rightskip \@tocrmarg
       \parfillskip -\rightskip
```

```
      \parindent \@nameuse{cft#2indent}\relax\@afterindenttrue
      \interlinepenalty\@M
      \leavevmode
      \@tempdima \@nameuse{cft#2numwidth}\relax
      \expandafter\let\expandafter\@cftbsnum\csname cft#2presnum\endcsname
      \expandafter\let\expandafter\@cftasnum\csname cft#2aftersnum\endcsname
      \expandafter\let\expandafter\@cftasnumb\csname cft#2aftersnumb\endcsname
      \advance\leftskip\@tempdima \null\nobreak\hskip -\leftskip
      \UseHookWithArguments{contentsline/text/before}{4}
        {\@nameuse{toclevel@#2}}{##1}{##2}{\@contentsline@destination}%
       {\@nameuse{cft#2font} ##1}\nobreak
      \UseHookWithArguments{contentsline/text/after}{4}
        {\@nameuse{toclevel@#2}}{##1}{##2}{\@contentsline@destination}%
      \@nameuse{cft#2fillnum}{##2}}%
  \fi
}  % end of \l@#2

```

Now define all the layout commands used by `\l@X`. The default values of these correspond to those for section entries in non-chaptered documents.

```
\expandafter\newlength\csname cftbefore#2skip\endcsname
  \setlength{\@nameuse{cftbefore#2skip}}{\z@ \@plus .2\p@}
```

\cftXindent
\cftXnumwidth

```
\expandafter\newlength\csname cft#2indent\endcsname
\expandafter\newlength\csname cft#2numwidth\endcsname
```

Set the default values for the indent and numwidth depending on the entry's level. A level of 1 corresponds to a figure entry.

```
\ifcase #4\relax  % 0
  \setlength{\@nameuse{cft#2indent}}{0em}
  \setlength{\@nameuse{cft#2numwidth}}{1.5em}
\or               % 1
  \setlength{\@nameuse{cft#2indent}}{1.5em}
  \setlength{\@nameuse{cft#2numwidth}}{2.3em}
\or               % 2
  \setlength{\@nameuse{cft#2indent}}{3.8em}
  \setlength{\@nameuse{cft#2numwidth}}{3.2em}
\or               % 3
  \setlength{\@nameuse{cft#2indent}}{7.0em}
  \setlength{\@nameuse{cft#2numwidth}}{4.1em}
\else             % anything else
  \setlength{\@nameuse{cft#2indent}}{10.0em}
  \setlength{\@nameuse{cft#2numwidth}}{5.0em}
\fi
```

And the remaining commands.

\cftXfont
\cftXpresnum
\cftXaftersnum
\cftXaftersnumb
\cftXdotsep
\cftXleader
\cftXpagefont
\cftXafterpnum
\cftXpnumfinal

```
\@namedef{cft#2font}{\normalfont}
\@namedef{cft#2presnum}{}
\@namedef{cft#2aftersnum}{}
\@namedef{cft#2aftersnumb}{}
\@namedef{cft#2dotsep}{\cftdotsep}
\@namedef{cft#2leader}{\normalfont\cftdotfill{\@nameuse{cft#2dotsep}}}
\@namedef{cft#2pagefont}{\normalfont}
```

```
\@namedef{cft#2afterpnum}{}
\@namedef{cft#2pnumfinal}{\cftpnumfinaldefault}
```

The hyperref package needs a command `\toclevel@X`, holding the ⟨*level*⟩ value.

`\toclevel@X`

```
\ExpandArgs{ce}\def{toclevel@#2}{\inteval{#4+1}}
```

Typeset the leader and page number.

`\cftXfillnum`

```
\@namedef{cft#2fillnum}##1{%
  {\UseTaggingSocket{toc/leaders/before}\SuspendTagging{toc/leaders}%
   \@nameuse{cft#2leader}%
   \ResumeTagging{toc/leaders}\UseTaggingSocket{toc/leaders/after}%
  }\nobreak
  \UseHookWithArguments{contentsline/page/before}{4}
    {\@nameuse{toclevel@#2}}{}{##1}{\@contentsline@destination}
  \makebox[\@pnumwidth][\cftpnumalign]{\@nameuse{cft#2pagefont}##1}%
  \UseHookWithArguments{contentsline/page/after}{4}
    {\@nameuse{toclevel@#2}}{}{##1}{\@contentsline@destination}%
   \@nameuse{cft#2afterpnum}\@nameuse{cft#2pnumfinal}\par
}
```

This ends the definition of `\newlistentry`.

```
}
```

(*End of definition for* `\newlistentry` *and others. These functions are documented on page 14.*)

`\newlistof`

`\newlistof[`⟨*within*⟩`]{`⟨*entry*⟩`}{`⟨*ext*⟩`}{`⟨*listofname*⟩`}` creates the commands for a new List of.

```
\newcommand{\newlistof}[4][\@empty]{%
```

Call `\newlistentry` to set up the first level entry.

```
  \ifx \@empty#1\relax
    \newlistentry{#2}{#3}{0}
  \else
    \newlistentry[#1]{#2}{#3}{0}
  \fi
```

(*End of definition for* `\newlistof`*. This function is documented on page 13.*)

`\ext@Z`
`\Zdepth`

The file extension and listing depth.

```
\@namedef{ext@#2}{#3}
\newcounter{#3depth}
\setcounter{#3depth}{1}
```

(*End of definition for* `\ext@Z` *and* `\Zdepth`.)

`\cftZtitlename`

```
\@namedef{cft#3titlename}{#4}
```

(*End of definition for* `\cftZtitlename`*. This function is documented on page 8.*)

`\cftmarkZ`

The heading marks for the listing.

```
\if@cftkoma
  \@namedef{cftmark#3}{%
    \@mkboth{\UseName{cft#3titlename}}{\UseName{cft#3titlename}}}
\else
```

```
    \@namedef{cftmark#3}{%
      \@mkboth{\MakeUppercase{\UseName{cft#3titlename}}}
              {\MakeUppercase{\UseName{cft#3titlename}}}}
  \fi
```

(*End of definition for* `\cftmarkZ`. *This function is documented on page 7.*)

`\listofX` Typeset the listing title and entries.

```
  \if@cftnctoc
```

For the titles option, basically copy the code from the standard `\tableofcontents` command.

```
    \@namedef{listof#2}{%
      \@cfttocstart
      \if@cfthaschapter
        \chapter*{\UseName{cft#3titlename}}
      \else
        \section*{\UseName{cft#3titlename}}
      \fi
      \@nameuse{cftmark#3}
      \@starttoc{#3}%
      \@cfttocfinish}
  \else
```

Otherwise use the fully parameterised definition.

```
    \@namedef{listof#2}{%
      \@cfttocstart
      \par
      \begingroup
        \parindent\z@ \parskip\cftparskip
        \@nameuse{@cftmake#3title}
        \@starttoc{#3}%
      \endgroup
      \@cfttocfinish}
  \fi
```

(*End of definition for* `\listofX`. *This function is documented on page 14.*)

`\@cftmakeZtitle` Typeset the title.

```
    \@namedef{@cftmake#3title}{\cfttitlecommand{#3}}%
```

(*End of definition for* `\@cftmakeZtitle`.)

`\cftbeforeZtitleskip` `\cftafterZtitleskip` `\cftZtitlefont` The skips before and after the title heading, and the title font. The default values depend on whether or not the document class has chapters.

```
    \expandafter\newlength\csname cftbefore#3titleskip\endcsname
    \expandafter\newlength\csname cftafter#3titleskip\endcsname
    \if@cfthaschapter
       \setlength{\@nameuse{cftbefore#3titleskip}}{50pt}
       \setlength{\@nameuse{cftafter#3titleskip}}{40pt}
       \if@cftkoma
         \@namedef{cft#3titlefont}{\size@chapter\sectfont}
       \else
         \@namedef{cft#3titlefont}{\normalfont\Huge\bfseries}
```

```
    \fi
  \else
    \setlength{\@nameuse{cftbefore#3titleskip}}{3.5ex \@plus 1ex \@minus .2ex}
    \setlength{\@nameuse{cftafter#3titleskip}}{2.3ex \@plus .2ex}
    \if@cftkoma
      \@namedef{cft#3titlefont}{\size@section\sectfont}
    \else
      \@namedef{cft#3titlefont}{\normalfont\Huge\bfseries}
    \fi
  \fi
```

(*End of definition for* `\cftbeforeZtitleskip`, `\cftafterZtitleskip`, *and* `\cftZtitlefont`. *These functions are documented on page 7.*)

`\cftafterZtitle` Something to go after the title.

```
  \@namedef{cftafter#3title}{}
```

(*End of definition for* `\cftafterZtitle`. *This function is documented on page 8.*)

`\cftZprehook` `\cftZposthook` Hooks before and after the list of entries.

```
  \@namedef{cft#3prehook}{}
  \@namedef{cft#3posthook}{}
```

This is the end of the definition of `\newlistof`.

```
}
```

(*End of definition for* `\cftZprehook` *and* `\cftZposthook`. *These functions are documented on page 17.*)

`\cftsetindents` `\cftsetindents{`⟨*entry*⟩`}{`⟨*indent*⟩`}{`⟨*numwidth*⟩`}` sets the *indent* and *numwidth* for entry ⟨*entry*⟩. The macro has to map between the external entry name and the internal shorthand.

```
\newcommand{\cftsetindents}[3]{%
  \def\@cftemp{#1}
  \ifx\@cftemp\cftchapname
    \@cftsetindents{chap}{#2}{#3}
  \else
    \ifx\@cftemp\cftsecname \@cftsetindents{sec}{#2}{#3}
    \else
      \ifx\@cftemp\cftsubsecname \@cftsetindents{subsec}{#2}{#3}
      \else
        \ifx\@cftemp\cftsubsubsecname \@cftsetindents{subsubsec}{#2}{#3}
        \else
          \ifx\@cftemp\cftparaname \@cftsetindents{para}{#2}{#3}
          \else
            \ifx\@cftemp\cftsubparaname \@cftsetindents{subpara}{#2}{#3}
            \else
              \ifx\@cftemp\cftfigname \@cftsetindents{fig}{#2}{#3}
              \else
                \ifx\@cftemp\cftsubfigname \@cftsetindents{subfig}{#2}{#3}
                \else
                  \ifx\@cftemp\cfttabname \@cftsetindents{tab}{#2}{#3}
                  \else
                    \ifx\@cftemp\cftsubtabname \@cftsetindents{subtab}{#2}{#3}
                    \else
                      \@cftsetindents{#1}{#2}{#3}
```

```
                    \fi
                  \fi
                \fi
              \fi
            \fi
          \fi
        \fi
      \fi
    \fi
  \fi
}
```

(*End of definition for* `\cftsetindents`. *This function is documented on page 11.*)

`\@cftsetindents` `\@cftsetindents{`⟨*X*⟩`}{`⟨*indent*⟩`}{`⟨*numwidth*⟩`}` is the internal version of `\cftsetindents`, where in this case ⟨*X*⟩ is the internal (shorthand) name of the entry.

```
\newcommand{\@cftsetindents}[3]{%
  \setlength{\@nameuse{cft#1indent}}{#2}
  \setlength{\@nameuse{cft#1numwidth}}{#3}
}
```

(*End of definition for* `\@cftsetindents`.)

3.3 Switching page numbering

`\@cftpnumoff` `\@cftpnumoff{`⟨*shorthand*⟩`}` is the workhorse for switching page numbering off. The ⟨*shorthand*⟩ argument is the shorthand name of the entry (e.g. `subsec` for `subsection`). The macro redefines the `\cftXnumfill` command so that there is no leader and the page number is ignored.

```
\newcommand{\@cftpnumoff}[1]{%
  \@namedef{cft#1fillnum}##1{\UseTaggingSocket{struct/end}%
    \cftparfillskip\@nameuse{cft#1afterpnum}\@nameuse{cft#1pnumfinal}\par}}
```

(*End of definition for* `\@cftpnumoff`.)

`\cftchapname` `\cftsecname` `\cftsubsecname` `\cftsubsubsecname` `\cftparaname` `\cftsubparaname` `\cftfigname` `\cftsubfigname` `\cfttabname` `\cftsubtabname`

Unfortunately an early design decision was the use shorthands like `sec` for `section`. For the page switching I need to be able to correlate the shorthands and longhands.

```
\newcommand*{\cftchapname}{chapter}
\newcommand*{\cftsecname}{section}
\newcommand*{\cftsubsecname}{subsection}
\newcommand*{\cftsubsubsecname}{subsubsection}
\newcommand*{\cftparaname}{paragraph}
\newcommand*{\cftsubparaname}{subparagraph}
\newcommand*{\cftfigname}{figure}
\newcommand*{\cftsubfigname}{subfigure}
\newcommand*{\cfttabname}{table}
\newcommand*{\cftsubtabname}{subtable}
```

(*End of definition for* `\cftchapname` *and others.*)

\cftpagenumbersoff The user level command for switching off page numbers is \cftpagenumbersoff{⟨*entry*⟩} where ⟨*entry*⟩ is the longhand name of the entry. The principal task of this macro is to determine the corresponding shorthand name of the ⟨*entry*⟩ and then call \@cftpnumoff to do the work. For part and user-defined entries the long- and short-hand entry names are identical.

```
\DeclareRobustCommand{\cftpagenumbersoff}[1]{%
  \def\@cftemp{#1}
  \ifx\@cftemp\cftchapname
    \@cftpnumoff{chap}
  \else
    \ifx\@cftemp\cftsecname \@cftpnumoff{sec}
    \else
      \ifx\@cftemp\cftsubsecname \@cftpnumoff{subsec}
      \else
        \ifx\@cftemp\cftsubsubsecname \@cftpnumoff{subsubsec}
        \else
          \ifx\@cftemp\cftparaname \@cftpnumoff{para}
          \else
            \ifx\@cftemp\cftsubparaname \@cftpnumoff{subpara}
            \else
              \ifx\@cftemp\cftfigname \@cftpnumoff{fig}
              \else
                \ifx\@cftemp\cftsubfigname \@cftpnumoff{subfig}
                \else
                  \ifx\@cftemp\cfttabname \@cftpnumoff{tab}
                  \else
                    \ifx\@cftemp\cftsubtabname \@cftpnumoff{subtab}
                    \else
                      \@cftpnumoff{#1}
                    \fi
                  \fi
                \fi
              \fi
            \fi
          \fi
        \fi
      \fi
    \fi
  \fi
}
```

(*End of definition for* \cftpagenumbersoff*. This function is documented on page 12.*)

\cftpagenumberson \cftpagenumberson{⟨*entry*⟩} is the user level command for reversing the corresponding \cftpagenumbersoff.

```
\DeclareRobustCommand{\cftpagenumberson}[1]{%
  \def\@cftemp{#1}
  \ifx\@cftemp\cftchapname
    \@cftpnumon{chap}
  \else
    \ifx\@cftemp\cftsecname \@cftpnumon{sec}
    \else
      \ifx\@cftemp\cftsubsecname \@cftpnumon{subsec}
```

```
      \else
        \ifx\@cftemp\cftsubsubsecname \@cftpnumon{subsubsec}
        \else
          \ifx\@cftemp\cftparaname \@cftpnumon{para}
          \else
            \ifx\@cftemp\cftsubparaname \@cftpnumon{subpara}
            \else
              \ifx\@cftemp\cftfigname \@cftpnumon{fig}
              \else
                \ifx\@cftemp\cftsubfigname \@cftpnumon{subfig}
                \else
                  \ifx\@cftemp\cfttabname \@cftpnumon{tab}
                  \else
                    \ifx\@cftemp\cftsubtabname \@cftpnumon{subtab}
                    \else
                      \@cftpnumon{#1}
                    \fi
                  \fi
                \fi
              \fi
            \fi
          \fi
        \fi
      \fi
    \fi
  \fi
}
```

(*End of definition for* `\cftpagenumberson`. *This function is documented on page 12.*)

`\@cftpnumon` `\@cftpnumon{`⟨*shorthand*⟩`}` is the workhorse for switching page numbering off. The ⟨*shorthand*⟩ argument is the shorthand name of the entry (e.g. `subsec` for `subsection`). The macro defines the `\cftXnumfill` command to correspond to the default definition.

```
\newcommand{\@cftpnumon}[1]{%
  \@namedef{cft#1fillnum}##1{%
    {\@nameuse{cft#1leader}}\nobreak
    \makebox[\@pnumwidth][\cftpnumalign]{\@nameuse{cft#1pagefont}##1}%
     \@nameuse{cft#1afterpnum}\@nameuse{cft#1pnumfinal}\par
  }%
}
```

(*End of definition for* `\@cftpnumon`.)

3.4 Experimental utilities

The code in this section is experimental but in the sense that the capabilities might be modified in the future rather than that the code does not work.

`\cftchapterprecis` This is experimental. `\cftchapterprecis{`⟨*text*⟩`}` typesets ⟨*text*⟩ at the point where it is called, and also adds ⟨*text*⟩ to the `.toc` file. It is expects to be called immediately after a `\chapter` command.

```
\newcommand{\cftchapterprecis}[1]{%
  \cftchapterprecishere{#1}
  \cftchapterprecistoc{#1}}
```

(*End of definition for* `\cftchapterprecis`. *This function is documented on page 16.*)

`\cftchapterprecishere` `\cftchapterprecishere{`⟨*text*⟩`}` typesets ⟨*text*⟩. It expects to be called immediately after a `\chapter` command. First add some negative vertical space to move it closer to the chapter heading.

```
\newcommand{\cftchapterprecishere}[1]{%
  \par\vspace*{-2\baselineskip}
```

Typeset its argument using italic font in a `quote` environment.

```
  \begin{quote}\textit{#1}\end{quote}
  \par\nobreak\@afterheading}
```

(*End of definition for* `\cftchapterprecishere`. *This function is documented on page 16.*)

`\cftchapterprecistoc` `\cftchapterprecistoc{`⟨*text*⟩`}` adds ⟨*text*⟩ to the `.toc` file. The ⟨*text*⟩ will be typeset within the same margins as the the title text of a `\chapter` heading, using an italic font.

```
\newcommand{\cftchapterprecistoc}[1]{\addtocontents{toc}{%
```

Start a group to localize changes to the paragraphing. Set the left margin to the chapter indent plus the chapter number width.

```
  {\UseTaggingSocket{struct/begin}{tag=\protect\UseStructureName{toc/item}}%
   \UseTaggingSocket{struct-mc}{tag=\protect\UseStructureName{toc/item/text}}}{%
  \leftskip \cftchapindent\relax
   \advance\leftskip \cftchapnumwidth\relax
```

Set the right hand margin to `\@tocrmarg`.

```
   \rightskip \@tocrmarg\relax
```

Typeset ⟨*text*⟩ using an italic font, then ensure that the paragraph is finished (to use the local skips). Finally close the group and we are done.

```
   \textit{#1}\protect\par}%
   \UseTaggingSocket{struct/end}}}}

```

(*End of definition for* `\cftchapterprecistoc`. *This function is documented on page 16.*)

`\cftlocalchange` `\cftlocalchange{`⟨*file*⟩`}{`⟨*pnumwidth*⟩`}{`⟨*tocrmarg*⟩`}` makes an entry into ⟨*file*⟩ to change the `\@pnumwidth` and the `\@tocrmarg` values.

```
\newcommand{\cftlocalchange}[3]{%
  \addtocontents{#1}{\protect\cftsetpnumwidth{#2} \protect\cftsetrmarg{#3}}}
```

(*End of definition for* `\cftlocalchange`. *This function is documented on page 16.*)

`\cftaddtitleline` `\cftaddtitleline{`⟨*file*⟩`}{`⟨*kind*⟩`}{`⟨*title*⟩`}{`⟨*page*⟩`}` adds a `\contentsline` entry to ⟨*file*⟩ with the given information.

```
\newcommand{\cftaddtitleline}[4]{\addtocontents{#1}{%
  \protect\contentsline{#2}{#3}{#4}{\@currentHref}\protected@file@percent}}
```

(*End of definition for* `\cftaddtitleline`. *This function is documented on page 16.*)

`\cftaddnumtitleline` `\cftaddnumtitleline{`⟨*file*⟩`}{`⟨*kind*⟩`}{`⟨*num*⟩`}{`⟨*title*⟩`}{`⟨*page*⟩`}` adds a `\contentsline` entry to ⟨*file*⟩ with the given information.

```
\newcommand{\cftaddnumtitleline}[5]{\addtocontents{#1}{%
  \protect\contentsline{#2}{\protect\numberline{#3}#4}{#5}{\@currentHref}%
    \protected@file@percent}}
```

(*End of definition for* `\cftaddnumtitleline`. *This function is documented on page 16.*)

And, if dear old hyperref has been used, we have to fix up these two macros. . Argument number is identical now.

`\@starttoc`

Okay, here's a roughly-comprehensive list where `\@starttoc` is redefined in TEX Live 2014.

- amsart, amsbook, amsdtx, amsproc
- asect
- latx.ltx (of course)
- newfloat
- flowfram
- gmampulex (?), gmtypos
- hyperref, memhfixc
- ijmart
- scrartcl, scrbook, scrreprt
- scrwtfile
- tocbasic
- tocstyle
- memoir
- multitoc
- nccsect
- notoccite
- artikel3, boek3, rapport3,
- rerunfilecheck
- parskip
- pdfwin
- revtex4
- devanagari

This makes things difficult if we want to redefine `\@starttoc` here. Many of the packages/classes above will not be used in conjunction with tocloft; on the other hand, we don't want to trample too much on others' code.
So for our own work here, let's be extra conservative, at least for now, and only hook into `\starttoc` if it's the standard LaTeX version.

```
\def\@starttoc@latex@orig#1{%
 \begingroup
   \makeatletter
   \@input{\jobname.#1}%
   \if@filesw
     \expandafter\newwrite\csname tf@#1\endcsname
     \immediate\openout \csname tf@#1\endcsname \jobname.#1\relax
   \fi
  \@nobreakfalse
\endgroup}
\newif\if@cft@patch@starttoc
\IfDocumentMetadataTF
 {
   \@cft@patch@starttoctrue
 }
 {
   \ifx\@starttoc\@starttoc@latex@orig
   \@cft@patch@starttoctrue
   \fi
 }

\if@cft@patch@starttoc
   \patchcmd\@starttoc
     {\begingroup}
     {\csname cft#1prehook\endcsname\begingroup}
     {}
     {%
      \PackageWarning{tocloft}
       {Patching of \string\@starttoc\space failed.\MessageBreak Prehook not inserted.}
     }
   \patchcmd\@starttoc
     {\endgroup}
     {\endgroup\csname cft#1posthook\endcsname}
     {}
     {%
      \PackageWarning{tocloft}
       {Patching of \string\@starttoc\space failed.\MessageBreak Posthook not inserted.}
     }
   \newcommand\cfttocprehook{}
   \newcommand\cftlofprehook{}
   \newcommand\cftlotprehook{}
   \newcommand\cfttocposthook{}
   \newcommand\cftlofposthook{}
   \newcommand\cftlotposthook{}
\else
   \PackageWarning{tocloft}{\string\@starttoc\space has already been redefined;
   \string\cfttocprehook\space et al. not installed.}
\fi
```

(*End of definition for* `\@starttoc`.)

The end of this package.

1393 ⟨/usc⟩

References

[Coc95] Steven Douglas Cochran. *The subfigure package*. March 1995. (Available from CTAN as file `subfigure.dtx`)

[Dru99] Jean-Pierre Drucbert. *The minitoc package*. August 1999. (Available from CTAN in subdirectory `/minitoc`)

[GMS94] Michel Goossens, Frank Mittelbach, and Alexander Samarin. *The LaTeX Companion*. Addison-Wesley Publishing Company, 1994.

[Lin97] Ulf A. Lindgren. *FncyChap V1.11*. April 1997. (Available from CTAN in subdirectory `/fncychap`)

[Lin95] Anselm Lingnau. *An Improved Environment for Floats*. March 1995. (Available from CTAN in subdirectory `/float`)

[Wil96a] Peter Williams. *Algorithms*. April 1996. (Available from CTAN in subdirectory `/algorithm`)

[Wil96b] Peter R. Wilson. *LaTeX for standards: The LaTeX package files user manual*. NIST Report NISTIR, June 1996.

[Wil00] Peter R. Wilson. *The tocbibind package*. March 2000. (Available from CTAN as file `tocbibind.dtx`)

[Wil01] Peter R. Wilson. *The ccaption package*. March 2001. (Available from CTAN as file `ccaption.dtx`)

Index

The italic numbers denote the pages where the corresponding entry is described, numbers underlined point to the definition, all others indicate the places where it is used.

Symbols

`\@cftasnum` *17*
`\@cftasnumb` *17*
`\@cftbsnum` *17*
`\@dotsep` *4*
`\@dottedtocline` *5*
`\@pnumwidth` *4*
`\@tocrmarg` *4*

A

`\addcontentsline` *3*
`\addcontentsline` 84, 87, 723, 726, 824, 827
`\addtocontents` *5*
`\addtocontents` 1330, 1340, 1341, 1343
`\AtBeginDocument` 18, 30, 224, 729, 831, 1034, 1036

B

`\baselineskip` 1327

C

`\cftaddnumtitleline` *16*
`\cftaddnumtitleline` 1343
`\cftaddtitleline` *16*

\cftaddtitleline 1341
\cftafterloftitle 756
\cftafterloftitleskip 747
\cftafterlottitle 858
\cftafterlottitleskip 849
\cftaftertoctitle 259
\cftaftertoctitleskip 250
\cftafterZtitle *8*
\cftafterZtitle *3*, 1184
\cftafterZtitleskip *7*
\cftafterZtitleskip 1165
\cftbeforechapskip 390, 410
\cftbeforefigskip 767, 787
\cftbeforeloftitleskip 747
\cftbeforelottitleskip 849
\cftbeforeparaskip 613, 632
\cftbeforepartskip 317, 350
\cftbeforesecskip 446, 449, 469
\cftbeforesubfigskip 921, 944
\cftbeforesubparaskip 667, 686
\cftbeforesubsecskip 509, 526
\cftbeforesubsubsecskip 561, 578
\cftbeforesubtabskip 979, 1001
\cftbeforetabskip 869, 889
\cftbeforetoctitleskip 250
\cftbeforeXskip *9*
\cftbeforeXskip 1080
\cftbeforeZtitleskip *7*
\cftbeforeZtitleskip 1165
\cftchapafterpnum 410
\cftchapaftersnum 399, 410
\cftchapaftersnumb 400, 410
\cftchapdotsep 410
\cftchapfillnum 407, 410
\cftchapfont 404, 410
\cftchapindent 391, 394, 410, 1333
\cftchapleader 410
\cftchapname 1190, 1233, 1246, 1282
\cftchapnumwidth 397, 410, 1334
\cftchappagefont 410
\cftchappnumfinal 410
\cftchappresnum 398, 410
\cftchapter *8*
\cftchapter 99, 103
\cftchapterprecis *16*
\cftchapterprecis 1323
\cftchapterprecishere *16*
\cftchapterprecishere 1324, 1326
\cftchapterprecistoc *16*
\cftchapterprecistoc 1325, 1330
\cftdot *8*
\cftdot 270
\cftdotfill 270, 360, 421, 480, 488, 541, 593, 647, 701, 797, 899, 954, 1011, 1105
\cftdotsep *9*
\cftdotsep 280, 481, 542, 594, 648, 702, 798, 900, 955, 1012, 1104
\cftfigafterpnum 787
\cftfigaftersnum 776, 787
\cftfigaftersnumb 777, 787
\cftfigdotsep 787
\cftfigfillnum 784, 787
\cftfigfont 781, 787
\cftfigindent 768, 771, 787
\cftfigleader 787
\cftfigname 1203, 1233, 1259, 1295
\cftfignumwidth 774, 787
\cftfigpagefont 787
\cftfigpnumfinal 787
\cftfigpresnum 775, 787
\cftlocalchange *16*
\cftlocalchange 1339
\cftlofposthook 1387
\cftlofprehook 1384
\cftloftitlefont 756
\cftloftitlename 55, 62, 96, 723, 726
\cftlotposthook 1388
\cftlotprehook 1385
\cftlottitlefont 858
\cftlottitlename 57, 64, 97, 824, 827
\cftmarklof 52
\cftmarklot 52
\cftmarktoc 52
\cftmarkZ *7*
\cftmarkZ 1133
\cftnodots *9*
\cftnodots 273, 280, 361, 422, 489
\cftpagenumbersoff *12*
\cftpagenumbersoff 1244
\cftpagenumberson *12*
\cftpagenumberson 1280
\cftparaafterpnum 632
\cftparaaftersnum 622, 632
\cftparaaftersnumb 623, 632
\cftparadotsep 632
\cftparafillnum 630, 632
\cftparafont 627, 632
\cftparaindent 614, 617, 632
\cftparaleader 632
\cftparaname 1199, 1233, 1255, 1291
\cftparanumwidth 620, 632
\cftparapagefont 632
\cftparapnumfinal 632
\cftparapresnum 621, 632
\cftparfillskip *12*
\cftparfillskip 282, 1231
\cftparskip *9*
\cftparskip 91, 226, 230, 239, 735, 837, 1157

\cftpartafterpnum 350
\cftpartaftersnum 328, 350
\cftpartaftersnumb 329, 350
\cftpartdotsep 350
\cftpartfillnum 336, 350
\cftpartfont 333, 350
\cftpartindent 319, 322, 350
\cftpartinitnumwidth *10*
\cftpartinitnumwidth 326, 356
\cftpartleader 350
\cftpartnumwidth 325, 350
\cftpartpagefont 350
\cftpartpnumfinal 350
\cftpartpresnum 327, 333, 350
\cftpnumalign *9*
\cftpnumalign *9*, 269, 375, 433, 502, 554, 606, 660, 714, 810, 912, 968, 1025, 1117, 1319
\cftpnumfinaldefault *11*
\cftpnumfinaldefault 94, 364, 425, 493, 545, 597, 651, 705, 801, 903, 958, 1015, 1108
\cftsecafterpnum 469
\cftsecaftersnum 459, 469
\cftsecaftersnumb 460, 469
\cftsecdotsep 469
\cftsecfillnum 467, 469
\cftsecfont 464, 469
\cftsecindent 451, 454, 469
\cftsecleader 469
\cftsecname 1193, 1233, 1249, 1285
\cftsecnumwidth 457, 469
\cftsecpagefont 469
\cftsecpnumfinal 469
\cftsecpresnum 458, 469
\cftsection *8*
\cftsection 101, 103
\cftsetindents *11*
\cftsetindents 1188
\cftsetpnumwidth *9*
\cftsetpnumwidth 267, 1340
\cftsetrmarg *9*
\cftsetrmarg 267, 1340
\cftsubfigafterpnum 944
\cftsubfigaftersnum 930, 944
\cftsubfigaftersnumb 931, 944
\cftsubfigdotsep 944
\cftsubfigfillnum 938, 944
\cftsubfigfont 935, 944
\cftsubfigindent 922, 925, 944
\cftsubfigleader 944
\cftsubfigname 1205, 1233, 1261, 1297
\cftsubfignumwidth 928, 944
\cftsubfigpagefont 944
\cftsubfigpnumfinal 944
\cftsubfigpresnum 929, 944
\cftsubparaafterpnum 686
\cftsubparaaftersnum 676, 686
\cftsubparaaftersnumb 677, 686
\cftsubparadotsep 686
\cftsubparafillnum 684, 686
\cftsubparafont 681, 686
\cftsubparaindent 668, 671, 686
\cftsubparaleader 686
\cftsubparaname . . . 1201, 1233, 1257, 1293
\cftsubparanumwidth 674, 686
\cftsubparapagefont 686
\cftsubparapnumfinal 686
\cftsubparapresnum 675, 686
\cftsubsecafterpnum 526, 557
\cftsubsecaftersnum 518, 526
\cftsubsecaftersnumb 519, 526
\cftsubsecdotsep 526
\cftsubsecfillnum 524, 546
\cftsubsecfont 522, 526
\cftsubsecindent 510, 513, 526
\cftsubsecleader 526, 549
\cftsubsecname 1195, 1233, 1251, 1287
\cftsubsecnumwidth 516, 526
\cftsubsecpagefont 526, 554
\cftsubsecpnumfinal 526, 557
\cftsubsecpresnum 517, 526
\cftsubsubsecafterpnum 578
\cftsubsubsecaftersnum 570, 578
\cftsubsubsecaftersnumb 571, 578
\cftsubsubsecdotsep 578
\cftsubsubsecfillnum 576, 578
\cftsubsubsecfont 574, 578
\cftsubsubsecindent 562, 565, 578
\cftsubsubsecleader 578
\cftsubsubsecname . 1197, 1233, 1253, 1289
\cftsubsubsecnumwidth 568, 578
\cftsubsubsecpagefont 578
\cftsubsubsecpnumfinal 578
\cftsubsubsecpresnum 569, 578
\cftsubtabafterpnum 1001
\cftsubtabaftersnum 988, 1001
\cftsubtabaftersnumb 989, 1001
\cftsubtabdotsep 954, 1001
\cftsubtabfillnum 996, 1001
\cftsubtabfont 993, 1001
\cftsubtabindent 980, 983, 1001
\cftsubtableader 1001
\cftsubtabname 1209, 1233, 1265, 1301
\cftsubtabnumwidth 986, 1001
\cftsubtabpagefont 1001
\cftsubtabpnumfinal 1001
\cftsubtabpresnum 987, 1001

\cftsubtagafterpnum 1028
\cftsubtagfillnum 1017
\cftsubtagleader 1020
\cftsubtagpagefont 1025
\cftsubtagpnumfinal 1028
\cfttabafterpnum 889
\cfttabaftersnum 878, 889
\cfttabaftersnumb 879, 889
\cfttabdotsep 889
\cfttabfillnum 886, 889
\cfttabfont 883, 889
\cfttabindent 870, 873, 889
\cfttableader 889
\cfttabname 1207, 1233, 1263, 1299
\cfttabnumwidth 876, 889
\cfttabpagefont 889
\cfttabpnumfinal 889
\cfttabpresnum 877, 889
\cfttitlecommand *8*
\cfttitlecommand . . 98, 249, 746, 848, 1164
\cfttocposthook *3*, 1386
\cfttocprehook *3*, 1383, 1391
\cfttoctitlefont 259
\cfttoctitlename 53, 60, 84, 87, 95
\cftXafterpnum *10*
\cftXafterpnum 1100
\cftXaftersnum *10*
\cftXaftersnum 1100
\cftXaftersnumb *10*
\cftXaftersnumb 1100
\cftXdotsep *10*
\cftXdotsep 1100
\cftXfillnum *10*
\cftXfillnum 1110
\cftXfont *10*
\cftXfont 1100
\cftXindent *9*
\cftXindent 1082
\cftXleader *10*
\cftXleader 1100
\cftXnumwidth *9*
\cftXnumwidth 1082
\cftXpagefont *10*
\cftXpagefont 1100
\cftXpnumfinal *10*
\cftXpnumfinal 1100
\cftXpresnum *10*
\cftXpresnum 1100
\cftZposthook *17*
\cftZposthook 1185
\cftZprehook *17*
\cftZprehook *17*, 1185
\cftZtitlefont *8*
\cftZtitlefont 1165
\cftZtitlename *8*
\cftZtitlename 95, 1132
\chapter 117, 160, 1145
\contentsline *3*
\contentsline 1342, 1344
\contentsname 95
\csname 5, 1050, 1051, 1067, 1068, 1069, 1080, 1082, 1083, 1165, 1166, 1351, 1352, 1369, 1377

D

\DeclareDocumentCommand 114, 135, 157, 178, 197, 210
\DeclareInstance 108, 130, 152, 174
\DeclareRobustCommand 1244, 1280
\dimeval 122, 142, 165, 185
\DocumentMetadata *2*, *3*, *8*, *21*

E

\edef 1050
\endcsname 5, 1050, 1051, 1067, 1068, 1069, 1080, 1082, 1083, 1165, 1166, 1351, 1352, 1369, 1377
\endinput 24
\ExpandArgs 1109

H

\Huge 260, 757, 859, 1173, 1181

I

\IfDocumentMetadataTF 104, 1357
\immediate 1352
\interlinepenalty 202, 215, 323, 395, 455, 514, 566, 618, 672, 772, 874, 926, 984, 1064
\inteval 1109

L

\l@X *14*
\Large 263, 760, 862
\large 355, 360, 362, 382, 383
\leaders 277
\leftskip 319, 330, 391, 401, 451, 461, 510, 520, 562, 572, 614, 624, 668, 678, 768, 778, 870, 880, 922, 932, 980, 990, 1060, 1070, 1333, 1334
\listfigurename 96
\listoffigures *7*
\listoffigures 729
\listoftables *7*
\listoftables 831
\listofX *14*
\listofX 1141
\listtablename 97
lofdepth 815
lotdepth 815

M

\makeatletter 1348
\makebox *9*, *25*, 375, 433, 502, 554, 606, 660, 714, 810, 912, 968, 1025, 1117, 1319
\MakeUppercase 53, 55, 57, 1138, 1139
\MessageBreak 35, 36, 37, 1373, 1381
\mkern 277

N

\newif 11, 12, 17, 29, 41, 44, 295, 296, 1356
\newlistentry *14*
\newlistentry 1041, 1125, 1127
\newlistof *13*
\newlistof 1123
\newwrite 1351
\nobreakspace 155
\noexpand 1051
\normalfont 260, 263, 479, 480, 482, 537, 541, 543, 589, 593, 595, 643, 647, 649, 697, 701, 703, 757, 760, 793, 797, 799, 859, 862, 895, 899, 901, 950, 954, 956, 1007, 1011, 1013, 1100, 1105, 1106, 1173, 1181
\numberline *4*
\numberline 283

O

\onecolumn 69
\openout 1352

P

\PackageError 1055
\PackageInfo 25, 27
\PackageWarning 22, 34, 1046, 1372, 1380, 1390
\par *3*
\parindent 239, 322, 394, 454, 513, 565, 617, 671, 735, 771, 837, 873, 925, 983, 1063, 1157
\parskip 230, 239, 735, 837, 1157
\patchcmd 1367, 1375
\phantomsection 78, 83, 86, 722, 725, 823, 826
\providecommand 66, 74, 78, 270, 271, 280, 959, 1016

R

\RequirePackage 2
\ResumeTagging 371, 429, 498, 550, 602, 656, 710, 806, 908, 964, 1021, 1113

S

\sectfont 261, 264, 382, 383, 439, 758, 761, 860, 863, 1171, 1179
\section 138, 181, 1147
\starttoc *56*
\string 1373, 1381, 1390, 1391
\SuspendTagging . . . 369, 427, 496, 548, 600, 654, 708, 804, 906, 962, 1019, 1111

T

\tableofcontents *7*
\tableofcontents 224
\tagpdfparaOff 145
\tagpdfparaOn 145
TEX and LATEX 2ε commands:
\@afterheading 124, 144, 167, 187, 208, 221, 1329
\@afterindenttrue 322, 394, 454, 513, 565, 617, 671, 771, 873, 925, 983, 1063
\@cft@patch@starttoctrue . 1359, 1363
\@cftasnum 288, 292, 328, 399, 459, 518, 570, 622, 676, 776, 878, 930, 988, 1068
\@cftasnumb 290, 292, 329, 400, 460, 519, 571, 623, 677, 777, 879, 931, 989, 1069
\@cftbsnum 288, 292, 327, 398, 458, 517, 569, 621, 675, 775, 877, 929, 987, 1067
\@cftdobiblof 719, 738
\@cftdobiblot 820, 840
\@cftdobibtoc 80, 242
\@cftdopartfalse 300
\@cftdoparttrue 303, 307
\@cftemp 1189, 1190, 1193, 1195, 1197, 1199, 1201, 1203, 1205, 1207, 1209, 1245, 1246, 1249, 1251, 1253, 1255, 1257, 1259, 1261, 1263, 1265, 1281, 1282, 1285, 1287, 1289, 1291, 1293, 1295, 1297, 1299, 1301
\@cfthaschapterfalse 20
\@cfthaschaptertrue 26
\@cfthaspartfalse 297
\@cfthasparttrue 297
\@cftifundefined 3, 19, 21, 297
\@cftinitnumwidth 283, 326
\@cftkomafalse 13
\@cftkomatrue 14, 15, 16
\@cftl@subfig 917, 1034, 1038
\@cftl@subtab 975, 1034, 1038
\@cftmakeZtitle 1164
\@cftmakeloftitle 736, 746
\@cftmakelottitle 838, 848
\@cftmaketoctitle 240, 249
\@cftnctocfalse 41
\@cftnctoctrue 42
\@cftpagestyle 48, 124, 144, 167, 187, 201, 214

\@cftpnumoff 1229, 1247, 1249, 1251, 1253, 1255, 1257, 1259, 1261, 1263, 1265, 1267
\@cftpnumon 1283, 1285, 1287, 1289, 1291, 1293, 1295, 1297, 1299, 1301, 1303, 1316
\@cftquit 10, 24, 28
\@cftsetindents 1191, 1193, 1195, 1197, 1199, 1201, 1203, 1205, 1207, 1209, 1211, 1224
\@cftsetsubfig 943, 1033, 1037
\@cftsetsubtab 1000, 1033, 1037
\@cftsubfigoptfalse 44
\@cftsubfigopttrue 45
\@cfttitlesectrue 18
\@cfttocbibindfalse 31
\@cfttocbibindtrue 31
\@cfttocfinish 66, 246, 742, 844, 1151, 1161
\@cfttocstart 66, 236, 732, 834, 1143, 1154
\@contentsline@destination 332, 335, 374, 377, 403, 406, 432, 435, 463, 466, 501, 504, 521, 523, 553, 556, 573, 575, 605, 608, 626, 629, 659, 662, 680, 683, 713, 716, 780, 783, 809, 812, 882, 885, 911, 914, 934, 937, 967, 970, 992, 995, 1024, 1027, 1072, 1075, 1116, 1119
\@currentHref 1342, 1344
\@eha 1055
\@firstoftwo 6
\@highpenalty 313, 389
\@ifclassloaded 14, 15, 16
\@ifpackagelater 33
\@ifpackageloaded 18, 31
\@ifundefined 106, 1042, 1046
\@namedef 1057, 1100, 1101, 1102, 1103, 1104, 1105, 1106, 1107, 1108, 1110, 1129, 1132, 1134, 1137, 1142, 1153, 1164, 1171, 1173, 1179, 1181, 1184, 1185, 1186, 1230, 1317
\@nameuse 1058, 1059, 1060, 1063, 1066, 1072, 1073, 1075, 1076, 1081, 1085, 1086, 1088, 1089, 1091, 1092, 1094, 1095, 1097, 1098, 1105, 1112, 1116, 1117, 1119, 1120, 1149, 1158, 1168, 1169, 1176, 1177, 1225, 1226, 1231, 1318, 1319, 1320
\@nobreakfalse 340, 344, 1354
\@nobreaktrue 339, 343
\@pnumwidth 267, 375, 433, 502, 554, 606, 660, 714, 810, 912, 968, 1025, 1117, 1319
\@restonecolfalse 71
\@restonecoltrue 69
\@secondoftwo 8
\@secpenalty 199, 212, 315, 448
\@starttoc *3*, *55*, *56*, 227, 228, 244, 740, 842, 1150, 1159, 1346
\@starttoc@latex@orig 1346, 1362
\@tempa 272, 274
\@tempb 273, 274
\@tocextra 87, 726, 827
\@tocrmarg 268, 320, 392, 452, 511, 563, 615, 669, 769, 871, 923, 981, 1061, 1335
\c@lofdepth 766, 919, 977
\c@lotdepth 868
\c@tocdepth 301, 305, 388, 444, 508, 560, 612, 666
\c@X 1042
\cft@listname 103
\ext@Z 1129
\hb@xt@ 286
\if@bibchapter 82, 721, 822
\if@cft@patch@starttoc . . . 1356, 1366
\if@cftdopart 295
\if@cfthaschapter 10, 67, 75, 98, 252, 259, 302, 306, 312, 338, 386, 410, 445, 475, 530, 582, 636, 690, 749, 756, 851, 858, 1144, 1167
\if@cfthaspart 296, 298, 350
\if@cftkoma 12, 58, 261, 264, 333, 380, 438, 758, 761, 860, 863, 1133, 1170, 1178
\if@cftnctoc . . . 41, 225, 730, 832, 1141
\if@cftsubfigopt . 44, 815, 1032, 1036
\if@cfttitlesec 17, 333
\if@cfttocbibind . . . 29, 241, 737, 839
\if@compatibility 342
\if@dotoclof 720
\if@dotoclot 821
\if@dotoctoc 81
\if@filesw 1350
\if@restonecol 76
\if@twocolumn 68
\l@ 1078
\l@chapter 386
\l@figure 765
\l@paragraph 611
\l@part 295
\l@section 443
\l@subfigure 918
\l@subparagraph 665
\l@subsection 507
\l@subsubsection 559
\l@subtable 976

\l@table 867
\l@X 1057
\OLD@starttoc 227, 231
\protected@file@percent . . 1342, 1345
\size@chapter 261, 758, 860, 1171
\size@section 264, 761, 863, 1179
\toclevel@subfig 944
\toclevel@subfigure 919, 934, 937, 959, 967, 970
\toclevel@subtable 977, 992, 995, 1001
\toclevel@X 1109
\textit 1328, 1336
\theX *14*
\theX 1042
\thispagestyle 49
\tocloftpagestyle *7*
\tocloftpagestyle 48
\topskip 122, 142, 165, 185
\twocolumn 76

U

\UseHookWithArguments 287, 289, 331, 334, 373, 376, 402, 405, 431, 434, 462, 465, 500, 503, 521, 523, 552, 555, 573, 575, 604, 607, 625, 628, 658, 661, 679, 682, 712, 715, 779, 782, 808, 811, 881, 884, 910, 913, 933, 936, 966, 969, 991, 994, 1023, 1026, 1071, 1074, 1115, 1118
\UseName 112, 122, 123, 125, 128, 133, 142, 143, 145, 148, 165, 166, 168, 170, 172, 185, 186, 188, 190, 192, 200, 203, 204, 205, 207, 213, 216, 217, 218, 220, 1135, 1138, 1139, 1145, 1147
\UseStructureName 1331, 1332
\UseTaggingSocket 369, 371, 427, 429, 496, 498, 548, 550, 600, 602, 654, 656, 708, 710, 804, 806, 906, 908, 962, 964, 1019, 1021, 1111, 1113, 1230, 1331, 1332, 1337

W

\WordSpaceAmount 111

Z

\Zdepth *8*
\Zdepth 1129
\ZZdepth *14*